



PyTango Documentation

Release 9.3.2

PyTango team

Apr 30, 2020

CONTENTS

1	Getting started	1
1.1	Installing	1
1.2	Compiling	2
1.3	Testing	2
2	Quick tour	3
2.1	Fundamental TANGO concepts	3
2.2	Minimum setup	4
2.3	Client	4
2.4	Server	5
3	ITango	11
4	Green mode	13
4.1	Client green modes	13
4.2	Server green modes	19
5	PyTango API	21
5.1	Data types	21
5.2	Client API	29
5.3	Server API	96
5.4	Database API	162
5.5	Encoded API	189
5.6	The Utilities API	195
5.7	Exception API	199
6	How to	205
6.1	How to contribute	205
6.2	Check the default TANGO host	205
6.3	Check TANGO version	205
6.4	Report a bug	206
6.5	Test the connection to the Device and get it's current state	206
6.6	Read and write attributes	206
6.7	Execute commands	207
6.8	Execute commands with more complex types	208
6.9	Work with Groups	208
6.10	Handle errors	208
6.11	Registering devices	208
6.12	Using clients with multiprocessing	210
6.13	Using clients with multithreading	211
6.14	Write a server	212
6.15	Server logging	214
6.16	Multiple device classes (Python and C++) in a server	216
6.17	Create attributes dynamically	217
6.18	Create/Delete devices dynamically	218

6.19	Write a server (original API)	219
7	How to Contribute	227
7.1	Workflow	227
7.2	reStructuredText and Sphinx	227
7.3	Source code standard	227
7.4	Using Docker for development	228
7.5	Releasing a new version	228
8	FAQ	233
9	PyTango Enhancement Proposals	235
9.1	TEP 1 - Device Server High Level API	235
9.2	TEP 2 - Tango database serverless	245
10	History of changes	251
10.1	Document revisions	251
10.2	Version history	252
11	Indexes	273
	Python Module Index	275
	Index	277

GETTING STARTED

1.1 Installing

1.1.1 Linux

PyTango is available on linux as an official debian/ubuntu package:

```
$ sudo apt-get install python-pytango
```

RPM packages are also available for RHEL & CentOS:

- CentOS 6 32bits
- CentOS 6 64bits
- CentOS 7 64bits
- Fedora 23 32bits
- Fedora 23 64bits

1.1.2 PyPi

You can also install the latest version from [PyPi](#).

First, make sure you have the following packages already installed (all of them are available from the major official distribution repositories):

- [boost-python](#) (including [boost-python-dev](#))
- [numpy](#)

Then install PyTango either from pip:

```
$ pip install PyTango
```

or `easy_install`:

```
$ easy_install -U PyTango
```

1.1.3 Windows

First, make sure [Python](#) and [numpy](#) are installed.

PyTango team provides a limited set of binary PyTango distributables for Windows XP/Vista/7/8. The complete list of binaries can be downloaded from [PyPI](#).

Select the proper windows package, download it and finally execute the installation wizard.

1.2 Compiling

1.2.1 Linux

Since PyTango 9 the build system used to compile PyTango is the standard python `setuptools`.

Besides the binaries for the three dependencies mentioned above, you also need the development files for the respective libraries.

You can get the latest `.tar.gz` from [PyPI](#) or directly the latest SVN checkout:

```
$ git clone https://github.com/tango-cs/pytango.git
$ cd pytango
$ python setup.py build
$ sudo python setup.py install
```

This will install PyTango in the system python installation directory. (Since PyTango9, *ITango* has been removed to a separate project and it will not be installed with PyTango.) If you wish to install in a different directory, replace the last line with:

```
1 $ # private installation to your user (usually ~/.local/lib/python<X>.<Y>/site-
   ↪ packages)
2 $ python setup.py install --user
3
4 $ # or specific installation directory
5 $ python setup.py install --prefix=/home/homer/local
```

1.2.2 Windows

On windows, PyTango must be built using MS VC++. Since it is rarely needed and the instructions are so complicated, I have chosen to place the how-to in a separate text file. You can find it in the source package under `doc/windows_notes.txt`.

1.3 Testing

To test the installation, import `tango` and check `tango.Release.version`:

```
$ python -c "import tango; print(tango.Release.version)"
9.3.2
```

Next steps: Check out the [Quick tour](#).

QUICK TOUR

This quick tour will guide you through the first steps on using PyTango.

2.1 Fundamental TANGO concepts

Before you begin there are some fundamental TANGO concepts you should be aware of.

Tango consists basically of a set of *devices* running somewhere on the network.

A device is identified by a unique case insensitive name in the format *<domain>/<family>/<member>*.
Examples: *LAB-01/PowerSupply/01*, *ID21/OpticsHutch/energy*.

Each device has a series of *attributes*, *pipes*, *properties* and *commands*.

An attribute is identified by a name in a device. It has a value that can be read. Some attributes can also be changed (read-write attributes). Each attribute has a well known, fixed data type.

A pipe is a kind of attribute. Unlike attributes, the pipe data type is structured (in the sense of C struct) and it is dynamic.

A property is identified by a name in a device. Usually, devices properties are used to provide a way to configure a device.

A command is also identified by a name. A command may or not receive a parameter and may or not return a value when it is executed.

Any device has **at least** a *State* and *Status* attributes and *State*, *Status* and *Init* commands. Reading the *State* or *Status* attributes has the same effect as executing the *State* or *Status* commands.

Each device has an associated *TANGO Class*. Most of the times the TANGO class has the same name as the object oriented programming class which implements it but that is not mandatory.

TANGO devices *live* inside a operating system process called *TANGO Device Server*. This server acts as a container of devices. A device server can host multiple devices of multiple TANGO classes. Devices are, therefore, only accessible when the corresponding TANGO Device Server is running.

A special TANGO device server called the *TANGO Database Server* will act as a naming service between TANGO servers and clients. This server has a known address where it can be reached. The machines that run TANGO Device Servers and/or TANGO clients, should export an environment variable called `TANGO_HOST` that points to the TANGO Database server address. Example: `TANGO_HOST=homer.lab.eu:10000`

2.2 Minimum setup

This chapter assumes you have already installed PyTango.

To explore PyTango you should have a running Tango system. If you are working in a facility/institute that uses Tango, this has probably already been prepared for you. You need to ask your facility/institute tango contact for the TANGO_HOST variable where Tango system is running.

If you are working in an isolate machine you first need to make sure the Tango system is installed and running (see [tango how to](#)).

Most examples here connect to a device called `sys/tg_test/1` that runs in a TANGO server called `TangoTest` with the instance name `test`. This server comes with the TANGO installation. The TANGO installation also registers the `test` instance. All you have to do is start the `TangoTest` server on a console:

```
$ TangoTest test
Ready to accept request
```

Note: if you receive a message saying that the server is already running, it just means that somebody has already started the test server so you don't need to do anything.

2.3 Client

Finally you can get your hands dirty. The first thing to do is start a python console and import the `tango` module. The following example shows how to create a proxy to an existing TANGO device, how to read and write attributes and execute commands from a python console:

```
>>> import tango

>>> # create a device object
>>> test_device = tango.DeviceProxy("sys/tg_test/1")

>>> # every device has a state and status which can be checked with:
>>> print(test_device.state())
RUNNING

>>> print(test_device.status())
The device is in RUNNING state.

>>> # this device has an attribute called "long_scalar". Let's see which value it_
↳has...
>>> data = test_device.read_attribute("long_scalar")

>>> # ...PyTango provides a shortcut to do the same:
>>> data = test_device["long_scalar"]

>>> # the result of reading an attribute is a DeviceAttribute python object.
>>> # It has a member called "value" which contains the value of the attribute
>>> data.value
136

>>> # Check the complete DeviceAttribute members:
>>> print(data)
DeviceAttribute[
data_format = SCALAR
  dim_x = 1
  dim_y = 0
```

(continues on next page)

(continued from previous page)

```

has_failed = False
  is_empty = False
    name = 'long_scalar'
  nb_read = 1
nb_written = 1
  quality = ATTR_VALID
r_dimension = AttributeDimension(dim_x = 1, dim_y = 0)
  time = TimeVal(tv_nsec = 0, tv_sec = 1399450183, tv_usec = 323990)
  type = DevLong
  value = 136
  w_dim_x = 1
  w_dim_y = 0
w_dimension = AttributeDimension(dim_x = 1, dim_y = 0)
  w_value = 0]

>>> # PyTango provides a handy pythonic shortcut to read the attribute value:
>>> test_device.long_scalar
136

>>> # Setting an attribute value is equally easy:
>>> test_device.write_attribute("long_scalar", 8776)

>>> # ... and a handy shortcut to do the same exists as well:
>>> test_device.long_scalar = 8776

>>> # TangoTest has a command called "DevDouble" which receives a number
>>> # as parameter and returns the same number as a result. Let's
>>> # execute this command:
>>> test_device.command_inout("DevDouble", 45.67)
45.67

>>> # PyTango provides a handy shortcut: it exports commands as device methods:
>>> test_device.DevDouble(45.67)
45.67

>>> # Introspection: check the list of attributes:
>>> test_device.get_attribute_list()
['ampli', 'boolean_scalar', 'double_scalar', '...', 'State', 'Status']

>>>

```

This is just the tip of the iceberg. Check the *DeviceProxy* for the complete API.

PyTango used to come with an integrated IPython based console called *ITango*, now moved to a separate project. It provides helpers to simplify console usage. You can use this console instead of the traditional python console. Be aware, though, that many of the *tricks* you can do in an *ITango* console cannot be done in a python program.

2.4 Server

Since PyTango 8.1 it has become much easier to program a Tango device server. PyTango provides some helpers that allow developers to simplify the programming of a Tango device server.

Before creating a server you need to decide:

1. The Tango Class name of your device (example: *PowerSupply*). In our example we will use the same name as the python class name.
2. The list of attributes of the device, their data type, access (read-only vs read-write), data_format (scalar, 1D, 2D)

3. The list of commands, their parameters and their result

In our example we will write a fake power supply device server. There will be a class called *PowerSupply* which will have attributes:

- *voltage* (scalar, read-only, numeric)
- *current* (scalar, read_write, numeric, expert mode)
- *noise* (2D, read-only, numeric)

pipes:

- *info* (read-only)

commands:

- *TurnOn* (argument: None, result: None)
- *TurnOff* (argument: None, result: None)
- *Ramp* (param: scalar, numeric; result: bool)

properties:

- *host* (string representing the host name of the actual power supply)
- *port* (port number in the host with default value = 9788)

Here is the code for the `power_supply.py`

```

1  #!/usr/bin/env python
2  # -*- coding: utf-8 -*-
3
4  """Demo power supply tango device server"""
5
6  import time
7  import numpy
8
9  from tango import AttrQuality, AttrWriteType, DispLevel, DevState, DebugIt
10 from tango.server import Device, attribute, command, pipe, device_property
11
12
13 class PowerSupply(Device):
14
15     voltage = attribute(label="Voltage", dtype=float,
16                       display_level=DispLevel.OPERATOR,
17                       access=AttrWriteType.READ,
18                       unit="V", format="8.4f",
19                       doc="the power supply voltage")
20
21     current = attribute(label="Current", dtype=float,
22                       display_level=DispLevel.EXPERT,
23                       access=AttrWriteType.READ_WRITE,
24                       unit="A", format="8.4f",
25                       min_value=0.0, max_value=8.5,
26                       min_alarm=0.1, max_alarm=8.4,
27                       min_warning=0.5, max_warning=8.0,
28                       fget="get_current",
29                       fset="set_current",
30                       doc="the power supply current")
31
32     noise = attribute(label="Noise",
33                     dtype=((int,)),
34                     max_dim_x=1024, max_dim_y=1024)
35
36     info = pipe(label='Info')
```

(continues on next page)

(continued from previous page)


```

37
38     host = device_property(dtype=str)
39     port = device_property(dtype=int, default_value=9788)
40
41     def init_device(self):
42         Device.init_device(self)
43         self.__current = 0.0
44         self.set_state(DevState.STANDBY)
45
46     def read_voltage(self):
47         self.info_stream("read_voltage(%s, %d)", self.host, self.port)
48         return 9.99, time.time(), AttrQuality.ATTR_WARNING
49
50     def get_current(self):
51         return self.__current
52
53     def set_current(self, current):
54         # should set the power supply current
55         self.__current = current
56
57     def read_info(self):
58         return 'Information', dict(manufacturer='Tango',
59                                   model='PS2000',
60                                   version_number=123)
61
62     @DebugIt()
63     def read_noise(self):
64         return numpy.random.random_integers(1000, size=(100, 100))
65
66     @command
67     def TurnOn(self):
68         # turn on the actual power supply here
69         self.set_state(DevState.ON)
70
71     @command
72     def TurnOff(self):
73         # turn off the actual power supply here
74         self.set_state(DevState.OFF)
75
76     @command(dtype_in=float, doc_in="Ramp target current",
77             dtype_out=bool, doc_out="True if ramping went well, "
78             "False otherwise")
79     def Ramp(self, target_current):
80         # should do the ramping
81         return True
82
83
84 if __name__ == "__main__":
85     PowerSupply.run_server()

```

Check the *high level server API* for the complete reference API. The *write a server how to* can help as well.

Before running this brand new server we need to register it in the Tango system. You can do it with Jive (*Jive->Edit->Create server*):



... or in a python script:

```
>>> import tango

>>> dev_info = tango.DbDevInfo()
>>> dev_info.server = "PowerSupply/test"
>>> dev_info._class = "PowerSupply"
>>> dev_info.name = "test/power_supply/1"

>>> db = tango.Database()
>>> db.add_device(dev_info)
```

After, you can run the server on a console with:

```
$ python power_supply.py test
Ready to accept request
```

Now you can access it from a python console:

```
>>> import tango

>>> power_supply = tango.DeviceProxy("test/power_supply/1")
>>> power_supply.state()
STANDBY

>>> power_supply.current = 2.3

>>> power_supply.current
2.3

>>> power_supply.TurnOn()
>>> power_supply.Ramp(2.1)
True
```

(continues on next page)


(continued from previous page)

```
>>> power_supply.state()
ON
```

Note: In this example, the name of the server and the name of the tango class are the same: *PowerSupply*. This pattern is enforced by the `run_server()` method. However, it is possible to run several tango classes in the same server. In this case, the server name would typically be the name of server file. See the `run()` function for further information.

ITANGO

ITango is a PyTango CLI based on IPython. It is designed to be used as an IPython profile.



```
ITango
tcoutinho@pc151:~$ itango
ITango 8.0.0 -- An interactive Tango client.

Running on top of Python 2.7.1, IPython 0.14.dev and PyTango 8.0.0

help      -> ITango's help system.
object?   -> Details about 'object'. ?object also works, ?? prints more.

IPython profile: tango

hint: Try typing: mydev = Device("<tab>

ITango [1]:
```

ITango is available since PyTango 7.1.2 and has been moved to a separate project since PyTango 9.2.0:

- [package and instructions on PyPI](#)
- [sources on GitHub](#)
- [documentation on pythonhosted](#)

GREEN MODE

PyTango supports cooperative green Tango objects. Since version 8.1 two *green* modes have been added: Futures and Gevent. In version 9.2.0 another one has been added: Asyncio.

Note: The preferred mode to use for new projects is Asyncio. Support for this mode will take priority over the others.

The Futures uses the standard python module `concurrent.futures`. The Gevent mode uses the well known `gevent` library. The newest, Asyncio mode, uses `asyncio` - a Python library for asynchronous programming (it's featured as a part of a standard Python distribution since version 3.5 of Python; it's available on PyPI for older ones).

You can set the PyTango green mode at a global level. Set the environment variable `PYTANGO_GREEN_MODE` to either `futures`, `gevent` or `asyncio` (case insensitive). If this environment variable is not defined the PyTango global green mode defaults to *Synchronous*.

4.1 Client green modes

You can also change the active global green mode at any time in your program:

```
>>> from tango import DeviceProxy, GreenMode
>>> from tango import set_green_mode, get_green_mode

>>> get_green_mode()
tango.GreenMode.Synchronous

>>> dev = DeviceProxy("sys/tg_test/1")
>>> dev.get_green_mode()
tango.GreenMode.Synchronous

>>> set_green_mode(GreenMode.Futures)
>>> get_green_mode()
tango.GreenMode.Futures

>>> dev.get_green_mode()
tango.GreenMode.Futures
```

As you can see by the example, the global green mode will affect any previously created *DeviceProxy* using the default *DeviceProxy* constructor parameters.

You can specify green mode on a *DeviceProxy* at creation time. You can also change the green mode at any time:

```
>>> from tango.futures import DeviceProxy
>>> dev = DeviceProxy("sys/tg_test/1")
```

(continues on next page)

(continued from previous page)

```
>>> dev.get_green_mode()
tango.GreenMode.Futures

>>> dev.set_green_mode(GreenMode.Synchronous)
>>> dev.get_green_mode()
tango.GreenMode.Synchronous
```

4.1.1 futures mode

Using `concurrent.futures` cooperative mode in PyTango is relatively easy:

```
>>> from tango.futures import DeviceProxy

>>> dev = DeviceProxy("sys/tg_test/1")
>>> dev.get_green_mode()
tango.GreenMode.Futures

>>> print(dev.state())
RUNNING
```

The `tango.futures.DeviceProxy()` API is exactly the same as the standard `DeviceProxy`. The difference is in the semantics of the methods that involve synchronous network calls (constructor included) which may block the execution for a relatively big amount of time. The list of methods that have been modified to accept *futures* semantics are, on the `tango.futures.DeviceProxy()`:

- Constructor
- `state()`
- `status()`
- `read_attribute()`
- `write_attribute()`
- `write_read_attribute()`
- `read_attributes()`
- `write_attributes()`
- `ping()`

So how does this work in fact? I see no difference from using the *standard* `DeviceProxy`. Well, this is, in fact, one of the goals: be able to use a *futures* cooperation without changing the API. Behind the scenes the methods mentioned before have been modified to be able to work cooperatively.

All of the above methods have been boosted with two extra keyword arguments *wait* and *timeout* which allow to fine tune the behaviour. The *wait* parameter is by default set to *True* meaning wait for the request to finish (the default semantics when not using green mode). If *wait* is set to *True*, the *timeout* determines the maximum time to wait for the method to execute. The default is *None* which means wait forever. If *wait* is set to *False*, the *timeout* is ignored.

If *wait* is set to *True*, the result is the same as executing the *standard* method on a `DeviceProxy`. If *wait* is set to *False*, the result will be a `concurrent.futures.Future`. In this case, to get the actual value you will need to do something like:

```
>>> from tango.futures import DeviceProxy

>>> dev = DeviceProxy("sys/tg_test/1")
>>> result = dev.state(wait=False)
>>> result
<Future at 0x16cb310 state=pending>
```

(continues on next page)

(continued from previous page)

```
>>> # this will be the blocking code
>>> state = result.result()
>>> print(state)
RUNNING
```

Here is another example using `read_attribute()`:

```
>>> from tango.futures import DeviceProxy

>>> dev = DeviceProxy("sys/tg_test/1")
>>> result = dev.read_attribute('wave', wait=False)
>>> result
<Future at 0x16cbe50 state=pending>

>>> dev_attr = result.result()
>>> print(dev_attr)
DeviceAttribute[
data_format = tango.AttrDataFormat.SPECTRUM
    dim_x = 256
    dim_y = 0
has_failed = False
is_empty = False
    name = 'wave'
    nb_read = 256
nb_written = 0
    quality = tango.AttrQuality.ATTR_VALID
r_dimension = AttributeDimension(dim_x = 256, dim_y = 0)
    time = TimeVal(tv_nsec = 0, tv_sec = 1383923329, tv_usec = 451821)
    type = tango.CmdArgType.DevDouble
    value = array([-9.61260664e-01, -9.65924853e-01, -9.70294813e-01,
-9.74369212e-01, -9.78146810e-01, -9.81626455e-01,
-9.84807087e-01, -9.87687739e-01, -9.90267531e-01,
...
5.150444507e-1])
w_dim_x = 0
w_dim_y = 0
w_dimension = AttributeDimension(dim_x = 0, dim_y = 0)
w_value = None]
```

4.1.2 gevent mode

Warning: Before using gevent mode please note that at the time of writing this documentation, `tango.gevent` requires the latest version 1.0 of gevent (which has been released the day before :-P).

Using `gevent` cooperative mode in PyTango is relatively easy:

```
>>> from tango.gevent import DeviceProxy

>>> dev = DeviceProxy("sys/tg_test/1")
>>> dev.get_green_mode()
tango.GreenMode.Gevent

>>> print(dev.state())
RUNNING
```

The `tango.gevent.DeviceProxy()` API is exactly the same as the standard `DeviceProxy`. The difference is in the semantics of the methods that involve synchronous network calls (constructor in-

cluded) which may block the execution for a relatively big amount of time. The list of methods that have been modified to accept *gevent* semantics are, on the `tango.gevent.DeviceProxy()`:

- Constructor
- `state()`
- `status()`
- `read_attribute()`
- `write_attribute()`
- `write_read_attribute()`
- `read_attributes()`
- `write_attributes()`
- `ping()`

So how does this work in fact? I see no difference from using the *standard* `DeviceProxy`. Well, this is, in fact, one of the goals: be able to use a *gevent* cooperation without changing the API. Behind the scenes the methods mentioned before have been modified to be able to work cooperatively with other *greenlets*.

All of the above methods have been boosted with two extra keyword arguments *wait* and *timeout* which allow to fine tune the behaviour. The *wait* parameter is by default set to *True* meaning wait for the request to finish (the default semantics when not using *green mode*). If *wait* is set to *True*, the *timeout* determines the maximum time to wait for the method to execute. The default *timeout* is *None* which means wait forever. If *wait* is set to *False*, the *timeout* is ignored.

If *wait* is set to *True*, the result is the same as executing the *standard* method on a `DeviceProxy`. If *wait* is set to *False*, the result will be a `gevent.event.AsyncResult`. In this case, to get the actual value you will need to do something like:

```
>>> from tango.gevent import DeviceProxy

>>> dev = DeviceProxy("sys/tg_test/1")
>>> result = dev.state(wait=False)
>>> result
<gevent.event.AsyncResult at 0x1a74050>

>>> # this will be the blocking code
>>> state = result.get()
>>> print(state)
RUNNING
```

Here is another example using `read_attribute()`:

```
>>> from tango.gevent import DeviceProxy

>>> dev = DeviceProxy("sys/tg_test/1")
>>> result = dev.read_attribute('wave', wait=False)
>>> result
<gevent.event.AsyncResult at 0x1aff54e>

>>> dev_attr = result.get()
>>> print(dev_attr)
DeviceAttribute[
data_format = tango.AttrDataFormat.SPECTRUM
  dim_x = 256
  dim_y = 0
has_failed = False
is_empty = False
  name = 'wave'
```

(continues on next page)

(continued from previous page)

```

    nb_read = 256
    nb_written = 0
    quality = tango.AttrQuality.ATTR_VALID
    r_dimension = AttributeDimension(dim_x = 256, dim_y = 0)
        time = TimeVal(tv_nsec = 0, tv_sec = 1383923292, tv_usec = 886720)
        type = tango.CmdArgType.DevDouble
        value = array([-9.61260664e-01, -9.65924853e-01, -9.70294813e-01,
            -9.74369212e-01, -9.78146810e-01, -9.81626455e-01,
            -9.84807087e-01, -9.87687739e-01, -9.90267531e-01,
            ...
            5.15044507e-1])
    w_dim_x = 0
    w_dim_y = 0
    w_dimension = AttributeDimension(dim_x = 0, dim_y = 0)
    w_value = None]

```

Note: due to the internal workings of `gevent`, setting the `wait` flag to `True` (default) doesn't prevent other greenlets from running in *parallel*. This is, in fact, one of the major bonus of working with `gevent` when compared with `concurrent.futures`

4.1.3 asyncio mode

`Asyncio` mode is similar to `gevent` but it uses explicit coroutines. You can compare `gevent` and `asyncio` examples.

```

1 import asyncio
2 from tango.asyncio import DeviceProxy
3
4 async def asyncio_example():
5     dev = await DeviceProxy("sys/tg_test/1")
6     print(dev.get_green_mode())
7
8     print(await dev.state())
9
10 loop = asyncio.get_event_loop()
11 loop.run_until_complete(asyncio_example())
12 loop.close()

```

Below you can find a TCP server example, which runs in an asynchronous mode and waits for a device's attribute name from a TCP client, then asks the device for a value and replies to the TCP client.

```

1 """A simple TCP server for Tango attributes.
2
3 It runs on all interfaces on port 8888:
4
5     $ python tango_tcp_server.py
6     Serving on 0.0.0.0 port 8888
7
8 It can be accessed using netcat:
9
10    $ ncat localhost 8888
11    >>> sys/tg_test/1/ampli
12    0.0
13    >>> sys/tg_test/1/state
14    RUNNING
15    >>> sys/tg_test/1/nope
16    DevFailed[

```

(continues on next page)

```

17     DevError[
18         desc = Attribute nope is not supported by device sys/tg_test/1
19         origin = AttributeProxy::real_constructor()
20         reason = API_UnsupportedAttribute
21         severity = ERR]
22     ]
23     >>> ...
24     """
25
26     import asyncio
27     from tango.asyncio import AttributeProxy
28
29
30     async def handle_echo(reader, writer):
31         # Write the cursor
32         writer.write(b'>>> ')
33         # Loop over client request
34         async for line in reader:
35             request = line.decode().strip()
36             # Get attribute value using asyncio green mode
37             try:
38                 proxy = await AttributeProxy(request)
39                 attr_value = await proxy.read()
40                 reply = str(attr_value.value)
41                 # Catch exception if something goes wrong
42                 except Exception as exc:
43                     reply = str(exc)
44                 # Reply to client
45                 writer.write(reply.encode() + b'\n' + b'>>> ')
46             # Close communication
47             writer.close()
48
49
50     async def start_serving():
51         server = await asyncio.start_server(handle_echo, '0.0.0.0', 8888)
52         print('Serving on {} port {}'.format(*server.sockets[0].getsockname()))
53         return server
54
55
56     async def stop_serving(server):
57         server.close()
58         await server.wait_closed()
59
60
61     def main():
62         # Start the server
63         loop = asyncio.get_event_loop()
64         server = loop.run_until_complete(start_serving())
65         # Serve requests until Ctrl+C is pressed
66         try:
67             loop.run_forever()
68         except KeyboardInterrupt:
69             pass
70         # Close the server
71         loop.run_until_complete(stop_serving(server))
72         loop.close()
73
74
75     if __name__ == '__main__':
76         main()

```

4.2 Server green modes

PyTango server API from version 9.2.0 supports two green modes: `Gevent` and `Asyncio`. Both can be used in writing new device servers in an asynchronous way.

4.2.1 gevent mode

This mode lets you convert your existing devices to asynchronous devices easily. You just add `green_mode = tango.GreenMode.Gevent` line to your device class. Consider this example:

```
class GeventDevice(Device):
    green_mode = tango.GreenMode.Gevent
```

Every method in your device class will be treated as a coroutine implicitly. This can be beneficial, but also potentially dangerous as it is a lot harder to debug. You should use this green mode with care. `Gevent` green mode is useful when you don't want to change too much in your existing code (or you don't feel comfortable with writing syntax of asynchronous calls).

Another thing to keep in mind is that when using `Gevent` green mode is that the Tango monitor lock is disabled, so the client requests can be processed concurrently.

Greenlets can also be used to spawn tasks in the background.

4.2.2 asyncio mode

The way `asyncio` green mode on the server side works is it redirects all user code to an event loop. This means that all user methods become coroutines, so in Python > 3.5 you should define them with `async` keyword. In Python < 3.5, you should use a `@coroutine` decorator. This also means that in order to convert existing code of your devices to `Asyncio` green mode you will have to introduce at least those changes. But, of course, to truly benefit from this green mode (and asynchronous approach in general), you should introduce more far-fetched changes!

The main benefit of asynchronous programming approach is that it lets you control precisely when code is run sequentially without interruptions and when control can be given back to the event loop. It's especially useful if you want to perform some long operations and don't want to prevent clients from accessing other parts of your device (attributes, in particular). This means that in `Asyncio` green mode there is no monitor lock!

The example below shows how `asyncio` can be used to write an asynchronous Tango device:

```
1  """Demo Tango Device Server using asyncio green mode"""
2
3  import asyncio
4  from tango import DevState, GreenMode
5  from tango.server import Device, command, attribute
6
7
8  class AsyncioDevice(Device):
9      green_mode = GreenMode.Asyncio
10
11     async def init_device(self):
12         await super().init_device()
13         self.set_state(DevState.ON)
14
15     @command
16     async def long_running_command(self):
17         self.set_state(DevState.OPEN)
18         await asyncio.sleep(2)
19         self.set_state(DevState.CLOSE)
```

(continues on next page)

(continued from previous page)

```
20
21     @command
22     async def background_task_command(self):
23         loop = asyncio.get_event_loop()
24         future = loop.create_task(self.coroutine_target())
25
26     async def coroutine_target(self):
27         self.set_state(DevState.INSERT)
28         await asyncio.sleep(15)
29         self.set_state(DevState.EXTRACT)
30
31     @attribute
32     async def test_attribute(self):
33         await asyncio.sleep(2)
34         return 42
35
36
37 if __name__ == '__main__':
38     AsyncioDevice.run_server()
```


PYTANGO API

This module implements the Python Tango Device API mapping.

5.1 Data types

This chapter describes the mapping of data types between Python and Tango.

Tango has more data types than Python which is more dynamic. The input and output values of the commands are translated according to the array below. Note that if PyTango is compiled with `numpy` support the `numpy` type will be the used for the input arguments. Also, it is recommended to use `numpy` arrays of the appropriate type for output arguments as well, as they tend to be much more efficient.

For scalar types (SCALAR)

Tango data type	Python 2.x type	Python 3.x type (<i>New in PyTango 8.0</i>)
DEV_VOID	No data	No data
DEV_BOOLEAN	<code>bool</code>	<code>bool</code>
DEV_SHORT	<code>int</code>	<code>int</code>
DEV_LONG	<code>int</code>	<code>int</code>
DEV_LONG64	<ul style="list-style-type: none"> <code>long</code> (on a 32 bits computer) <code>int</code> (on a 64 bits computer) 	<code>int</code>
DEV_FLOAT	<code>float</code>	<code>float</code>
DEV_DOUBLE	<code>float</code>	<code>float</code>
DEV_USHORT	<code>int</code>	<code>int</code>
DEV_ULONG	<code>int</code>	<code>int</code>
DEV_ULONG64	<ul style="list-style-type: none"> <code>long</code> (on a 32 bits computer) <code>int</code> (on a 64 bits computer) 	<code>int</code>
DEV_STRING	<code>str</code>	<code>str</code> (decoded with <i>latin-1</i> , aka <i>ISO-8859-1</i>)
DEV_ENCODED (<i>New in PyTango 8.0</i>)	sequence of two elements: <ol style="list-style-type: none"> <code>str</code> <code>bytes</code> (for any value of <i>extract_as</i>) 	sequence of two elements: <ol style="list-style-type: none"> <code>str</code> (decoded with <i>latin-1</i>, aka <i>ISO-8859-1</i>) <code>bytes</code> (for any value of <i>extract_as</i>, except <code>String</code>. In this case it is <code>str</code> (decoded with default python encoding <i>utf-8</i>))
DEV_ENUM (<i>New in PyTango 9.0</i>)	<ul style="list-style-type: none"> <code>int</code> (for value) <code>list <str></code> (for <code>enum_labels</code>) <p>Note: direct attribute access via type <code>enum.IntEnum</code>. This type uses the package <code>enum34</code>.</p>	<ul style="list-style-type: none"> <code>int</code> (for value) <code>list <str></code> (for <code>enum_labels</code>) <p>Note: direct attribute access via type <code>enum.IntEnum</code>. Python < 3.4, uses the package <code>enum34</code>. Python >= 3.4, uses standard package <code>enum</code>.</p>

For array types (SPECTRUM/IMAGE)

Tango data type	ExtractAs	Data type (Python 2.x)	Data type (Python 3.x) (<i>New in PyTango 8.0</i>)
DEVVAR_CHARARRAY	Numpy	<code>numpy.ndarray</code> (dtype= <code>numpy.uint8</code>)	<code>numpy.ndarray</code> (dtype= <code>numpy.uint8</code>)
	Bytes	<code>bytes</code> (which is in fact equal to <code>str</code>)	<code>bytes</code>
	ByteArray	<code>bytearray</code>	<code>bytearray</code>

continues on next page

Table 1 – continued from previous page

Tango data type	ExtractAs	Data type (Python 2.x)	Data type (Python 3.x) (New in PyTango 8.0)
	String	<code>str</code>	<code>str</code> (decoded with <i>latin-1</i> , aka ISO-8859-1)
	List	<code>list <int></code>	<code>list <int></code>
	Tuple	<code>tuple <int></code>	<code>tuple <int></code>
DEVVAR_SHORTARRAY or (DEV_SHORT + SPECTRUM) or (DEV_SHORT + IMAGE)	Numpy	<code>numpy.ndarray</code> (dtype= <code>numpy.uint16</code>)	<code>numpy.ndarray</code> (dtype= <code>numpy.uint16</code>)
	Bytes	<code>bytes</code> (which is in fact equal to <code>str</code>)	<code>bytes</code>
	ByteArray	<code>bytearray</code>	<code>bytearray</code>
	String	<code>str</code>	<code>str</code> (decoded with <i>latin-1</i> , aka ISO-8859-1)
	List	<code>list <int></code>	<code>list <int></code>
	Tuple	<code>tuple <int></code>	<code>tuple <int></code>
DEVVAR_LONGARRAY or (DEV_LONG + SPECTRUM) or (DEV_LONG + IMAGE)	Numpy	<code>numpy.ndarray</code> (dtype= <code>numpy.uint32</code>)	<code>numpy.ndarray</code> (dtype= <code>numpy.uint32</code>)
	Bytes	<code>bytes</code> (which is in fact equal to <code>str</code>)	<code>bytes</code>
	ByteArray	<code>bytearray</code>	<code>bytearray</code>
	String	<code>str</code>	<code>str</code> (decoded with <i>latin-1</i> , aka ISO-8859-1)
	List	<code>list <int></code>	<code>list <int></code>
	Tuple	<code>tuple <int></code>	<code>tuple <int></code>
DEVVAR_LONG64ARRAY or (DEV_LONG64 + SPECTRUM) or (DEV_LONG64 + IMAGE)	Numpy	<code>numpy.ndarray</code> (dtype= <code>numpy.uint64</code>)	<code>numpy.ndarray</code> (dtype= <code>numpy.uint64</code>)
	Bytes	<code>bytes</code> (which is in fact equal to <code>str</code>)	<code>bytes</code>
	ByteArray	<code>bytearray</code>	<code>bytearray</code>
	String	<code>str</code>	<code>str</code> (decoded with <i>latin-1</i> , aka ISO-8859-1)
	List	<code>list <int (64 bits) / long (32 bits)></code>	<code>list <int></code>
	Tuple	<code>tuple <int (64 bits) / long (32 bits)></code>	<code>tuple <int></code>
DEVVAR_FLOATARRAY or (DEV_FLOAT + SPECTRUM) or (DEV_FLOAT + IMAGE)	Numpy	<code>numpy.ndarray</code> (dtype= <code>numpy.float32</code>)	<code>numpy.ndarray</code> (dtype= <code>numpy.float32</code>)
	Bytes	<code>bytes</code> (which is in fact equal to <code>str</code>)	<code>bytes</code>
	ByteArray	<code>bytearray</code>	<code>bytearray</code>
	String	<code>str</code>	<code>str</code> (decoded with <i>latin-1</i> , aka ISO-8859-1)
	List	<code>list <float></code>	<code>list <float></code>
	Tuple	<code>tuple <float></code>	<code>tuple <float></code>
DEVVAR_DOUBLEARRAY or (DEV_DOUBLE + SPECTRUM) or (DEV_DOUBLE + IMAGE)	Numpy	<code>numpy.ndarray</code> (dtype= <code>numpy.float64</code>)	<code>numpy.ndarray</code> (dtype= <code>numpy.float64</code>)

continues on next page

Table 1 – continued from previous page

Tango data type	ExtractAs	Data type (Python 2.x)	Data type (Python 3.x) (<i>New in PyTango 8.0</i>)
	Bytes	<code>bytes</code> (which is in fact equal to <code>str</code>)	<code>bytes</code>
	ByteArray	<code>bytearray</code>	<code>bytearray</code>
	String	<code>str</code>	<code>str</code> (decoded with <i>latin-1</i> , aka <i>ISO-8859-1</i>)
	List	<code>list <float></code>	<code>list <float></code>
	Tuple	<code>tuple <float></code>	<code>tuple <float></code>
DEVVAR_USHORTARRAY or (DEV_USHORT + SPECTRUM) or (DEV_USHORT + IMAGE)	Numpy	<code>numpy.ndarray</code> (<code>dtype= numpy. uint16</code>)	<code>numpy.ndarray</code> (<code>dtype= numpy. uint16</code>)
	Bytes	<code>bytes</code> (which is in fact equal to <code>str</code>)	<code>bytes</code>
	ByteArray	<code>bytearray</code>	<code>bytearray</code>
	String	<code>str</code>	<code>str</code> (decoded with <i>latin-1</i> , aka <i>ISO-8859-1</i>)
	List	<code>list <int></code>	<code>list <int></code>
	Tuple	<code>tuple <int></code>	<code>tuple <int></code>
DEVVAR_ULONGARRAY or (DEV_ULONG + SPECTRUM) or (DEV_ULONG + IMAGE)	Numpy	<code>numpy.ndarray</code> (<code>dtype= numpy. uint32</code>)	<code>numpy.ndarray</code> (<code>dtype= numpy. uint32</code>)
	Bytes	<code>bytes</code> (which is in fact equal to <code>str</code>)	<code>bytes</code>
	ByteArray	<code>bytearray</code>	<code>bytearray</code>
	String	<code>str</code>	<code>str</code> (decoded with <i>latin-1</i> , aka <i>ISO-8859-1</i>)
	List	<code>list <int></code>	<code>list <int></code>
	Tuple	<code>tuple <int></code>	<code>tuple <int></code>
DEVVAR_ULONG64ARRAY or (DEV_ULONG64 + SPECTRUM) or (DEV_ULONG64 + IMAGE)	Numpy	<code>numpy.ndarray</code> (<code>dtype= numpy. uint64</code>)	<code>numpy.ndarray</code> (<code>dtype= numpy. uint64</code>)
	Bytes	<code>bytes</code> (which is in fact equal to <code>str</code>)	<code>bytes</code>
	ByteArray	<code>bytearray</code>	<code>bytearray</code>
	String	<code>str</code>	<code>str</code> (decoded with <i>latin-1</i> , aka <i>ISO-8859-1</i>)
	List	<code>list <int (64 bits) / long (32 bits)></code>	<code>list <int></code>
	Tuple	<code>tuple <int (64 bits) / long (32 bits)></code>	<code>tuple <int></code>
DEVVAR_STRINGARRAY or (DEV_STRING + SPECTRUM) or (DEV_STRING + IMAGE)		<code>sequence<str></code>	<code>sequence<str></code> (de- coded with <i>latin-1</i> , aka <i>ISO-8859-1</i>)

continues on next page

Table 1 – continued from previous page

Tango data type	ExtractAs	Data type (Python 2.x)	Data type (Python 3.x) (New in PyTango 8.0)
DEV_LONGSTRINGARRAY		sequence of two elements: 0. <code>numpy.ndarray</code> (<code>dtype= numpy.int32</code>) or <code>sequence<int></code> 1. <code>sequence<str></code>	sequence of two elements: 0. <code>numpy.ndarray</code> (<code>dtype= numpy.int32</code>) or <code>sequence<int></code> 1. <code>sequence<str></code> (decoded with <i>latin-1</i> , aka <i>ISO-8859-1</i>)
DEV_DOUBLESTRINGARRAY		sequence of two elements: 0. <code>numpy.ndarray</code> (<code>dtype= numpy.float64</code>) or <code>sequence<int></code> 1. <code>sequence<str></code>	sequence of two elements: 0. <code>numpy.ndarray</code> (<code>dtype= numpy.float64</code>) or <code>sequence<int></code> 1. <code>sequence<str></code> (decoded with <i>latin-1</i> , aka <i>ISO-8859-1</i>)

For SPECTRUM and IMAGES the actual sequence object used depends on the context where the tango data is used, and the availability of `numpy`.

1. for properties the sequence is always a `list`. Example:

```
>>> import tango
>>> db = tango.Database()
>>> s = db.get_property(["TangoSynchrotrons"])
>>> print type(s)
<type 'list'>
```

2. for attribute/command values

- `numpy.ndarray` if PyTango was compiled with `numpy` support (default) and `numpy` is installed.
- `list` otherwise

5.1.1 Pipe data types

Pipes require different data types. You can think of them as a structured type.

A pipe transports data which is called a *blob*. A *blob* consists of name and a list of fields. Each field is called *data element*. Each *data element* consists of a name and a value. *Data element* names must be unique in the same blob.

The value can be of any of the SCALAR or SPECTRUM tango data types (except `DevEnum`).

Additionally, the value can be a *blob* itself.

In PyTango, a *blob* is represented by a sequence of two elements:

- blob name (str)

- data is either:
 - sequence (`list`, `tuple`, or other) of data elements where each element is a `dict` with the following keys:
 - * *name* (mandatory): (`str`) data element name
 - * *value* (mandatory): data (compatible with any of the SCALAR or SPECTRUM data types except `DevEnum`). If value is to be a sub-*blob* then it should be sequence of [*blob name*, sequence of data elements] (see above)
 - * *dtype* (optional, mandatory if a `DevEncoded` is required): see *Data type equivalence*. If *dtype* key is not given, PyTango will try to find the proper tango type by inspecting the value.
 - a `dict` where key is the data element name and value is the data element value (compact version)

When using the compact dictionary version note that the order of the data elements is lost. If the order is important for you, consider using `collections.OrderedDict` instead (if you have python ≥ 2.7). If not you can use `orderdict` backport module available on pypi). Also, in compact mode it is not possible to enforce a specific type. As a consequence, `DevEncoded` is not supported in compact mode.

The description sounds more complicated that it actually is. Here are some practical examples of what you can return in a server as a read request from a pipe:

```
import numpy as np

# plain (one level) blob showing different tango data types
# (explicitly and implicit):

PIPE0 = \
('BlobCase0',
 ({'name': 'DE1', 'value': 123,}, # converts to_
 ↪DevLong64
 {'name': 'DE2', 'value': np.int32(456)}, # converts to_
 ↪DevLong
 {'name': 'DE3', 'value': 789, 'dtype': 'int32'}, # converts to_
 ↪DevLong
 {'name': 'DE4', 'value': np.uint32(123)}, # converts to_
 ↪DevULong
 {'name': 'DE5', 'value': range(5), 'dtype': ('uint16',)}, # converts to_
 ↪DevVarUShortArray
 {'name': 'DE6', 'value': [1.11, 2.22], 'dtype': ('float64',)}, # converts to_
 ↪DevVarDoubleArray
 {'name': 'DE7', 'value': numpy.zeros((100,))}, # converts to_
 ↪DevVarDoubleArray
 {'name': 'DE8', 'value': True}, # converts to_
 ↪DevBoolean
 )
)

# similar as above but in compact version (implicit data type conversion):

PIPE1 = \
('BlobCase1', dict(DE1=123, DE2=np.int32(456), DE3=np.int32(789),
                   DE4=np.uint32(123), DE5=np.arange(5, dtype='uint16'),
                   DE6=[1.11, 2.22], DE7=numpy.zeros((100,)),
                   DE8=True)
)

# similar as above but order matters so we use an ordered dict:
```

(continues on next page)

(continued from previous page)

```

import collections

data = collections.OrderedDict()
data['DE1'] = 123
data['DE2'] = np.int32(456)
data['DE3'] = np.int32(789)
data['DE4'] = np.uint32(123)
data['DE5'] = np.arange(5, dtype='uint16')
data['DE6'] = [1.11, 2.22]
data['DE7'] = numpy.zeros((100,))
data['DE8'] = True

PIPE2 = 'BlobCase2', data

# another plain blob showing string, string array and encoded data types:

PIPE3 = \
('BlobCase3',
 ({'name': 'stringDE', 'value': 'Hello'},
  {'name': 'VectorStringDE', 'value': ('bonjour', 'le', 'monde')},
  {'name': 'DevEncodedDE', 'value': ('json', '"isn\'t it?")', 'dtype': 'bytes'},
 )
)

# blob with sub-blob which in turn has a sub-blob

PIPE4 = \
('BlobCase4',
 ({'name': '1DE', 'value': ('Inner', (({'name': '1_1DE', 'value': 'Grenoble'},
                                     {'name': '1_2DE', 'value': ('InnerInner',
                                                                (({'name': '1_1_1_1DE', 'value': np.int32(111)},
                                                                (({'name': '1_1_1_2DE', 'value': [3.33]}))
                                                                ))
                                                                ))
                                     ))
                                     ))
  {'name': '2DE', 'value': (3,4,5,6), 'dtype': ('int32',) },
 )
)
)

```

5.1.2 DevEnum pythonic usage

When using regular tango DeviceProxy and AttributeProxy DevEnum is treated just like in cpp tango (see [enumerated attributes](#) for more info). However, since PyTango >= 9.2.5 there is a more pythonic way of using DevEnum data types if you use the *high level API*, both in server and client side.

In server side you can use python `enum.IntEnum` class to deal with DevEnum attributes:

```

import time
from enum import IntEnum
from tango import AttrWriteType
from tango.server import Device, attribute, command

class Noon(IntEnum):
    AM = 0 # DevEnum's must start at 0
    PM = 1 # and increment by 1

```

(continues on next page)

(continued from previous page)

```

class DisplayType(IntEnum):
    ANALOG = 0 # DevEnum's must start at 0
    DIGITAL = 1 # and increment by 1

class Clock(Device):

    display_type = DisplayType(0)

    @attribute(dtype=float)
    def time(self):
        return time.time()

    gmtime = attribute(dtype=(int,), max_dim_x=9)

    def read_gmtime(self):
        return time.gmtime()

    @attribute(dtype=Noon)
    def noon(self):
        time_struct = time.gmtime(time.time())
        return Noon.AM if time_struct.tm_hour < 12 else Noon.PM

    display = attribute(dtype=DisplayType, access=AttrWriteType.READ_WRITE)

    def read_display(self):
        return self.display_type

    def write_display(self, display_type):
        self.display_type = display_type

    @command(dtype_in=float, dtype_out=str)
    def ctime(self, seconds):
        """
        Convert a time in seconds since the Epoch to a string in local time.
        This is equivalent to asctime(localtime(seconds)). When the time tuple
        is not present, current time as returned by localtime() is used.
        """
        return time.ctime(seconds)

    @command(dtype_in=(int,), dtype_out=float)
    def mktime(self, tupl):
        return time.mktime(tupl)

if __name__ == "__main__":
    Clock.run_server()

```

On the client side you can also use a pythonic approach for using DevEnum attributes:

```

import sys
import PyTango

if len(sys.argv) != 2:
    print("must provide one and only one clock device name")
    sys.exit(1)

clock = PyTango.DeviceProxy(sys.argv[1])
t = clock.time
gmt = clock.gmtime
noon = clock.noon

```

(continues on next page)

(continued from previous page)

```

display = clock.display
print(t)
print(gmt)
print(noon, noon.name, noon.value)
if noon == noon.AM:
    print('Good morning!')
print(clock.ctime(t))
print(clock.mktime(gmt))
print(display, display.name, display.value)
clock.display = display.ANALOG
clock.display = 'DIGITAL' # you can use a valid string to set the value
print(clock.display, clock.display.name, clock.display.value)
display_type = type(display) # or even create your own IntEnum type
analog = display_type(0)
clock.display = analog
print(clock.display, clock.display.name, clock.display.value)
clock.display = clock.display.DIGITAL
print(clock.display, clock.display.name, clock.display.value)

```

5.2 Client API

5.2.1 DeviceProxy

```
class tango.DeviceProxy(*args, **kwargs)
```

Bases: `_tango.Connection`

DeviceProxy is the high level Tango object which provides the client with an easy-to-use interface to TANGO devices. DeviceProxy provides interfaces to all TANGO Device interfaces. The DeviceProxy manages timeouts, stateless connections and reconnection if the device server is restarted. To create a DeviceProxy, a Tango Device name must be set in the object constructor.

Example: `dev = tango.DeviceProxy("sys/tg_test/1")`

```
DeviceProxy(dev_name, green_mode=None, wait=True, timeout=True) -> DeviceProxy
DeviceProxy(self, dev_name, need_check_acc, green_mode=None, wait=True, timeout=True) -> DeviceProxy
```

Creates a new *DeviceProxy*.

Parameters

- **dev_name** (*str*) – the device name or alias
- **need_check_acc** (*bool*) – in first version of the function it defaults to True. Determines if at creation time of DeviceProxy it should check for channel access (rarely used)
- **green_mode** (*GreenMode*) – determines the mode of execution of the device (including the way it is created). Defaults to the current global green_mode (check `get_green_mode()` and `set_green_mode()`)
- **wait** (*bool*) – whether or not to wait for result. If green_mode Ignored when green_mode is Synchronous (always waits).
- **timeout** (*float*) – The number of seconds to wait for the result. If None, then there is no limit on the wait time. Ignored when green_mode is Synchronous or wait is False.

Returns

if **green_mode** is Synchronous or **wait** is True: *DeviceProxy*

elif green_mode is Futures: `concurrent.futures.Future`

elif green_mode is Gevent: `gevent.event.AsyncResult`

Throws

- : class:*~tango.DevFailed* if green_mode is Synchronous or wait is True and there is an error creating the device.
- : class:*concurrent.futures.TimeoutError* if green_mode is Futures, wait is False, timeout is not None and the time to create the device has expired.
- : class:*gevent.timeout.Timeout* if green_mode is Gevent, wait is False, timeout is not None and the time to create the device has expired.

New in version 8.1.0: *green_mode* parameter. *wait* parameter. *timeout* parameter.

add_logging_target (*self*, *target_type_target_name*) → `None`

Adds a new logging target to the device.

The *target_type_target_name* input parameter must follow the format: *target_type::target_name*. Supported target types are: console, file and device. For a device target, the *target_name* part of the *target_type_target_name* parameter must contain the name of a log consumer device (as defined in A.8). For a file target, *target_name* is the full path to the file to log to. If omitted, the device's name is used to build the file name (which is something like *domain_family_member.log*). Finally, the *target_name* part of the *target_type_target_name* input parameter is ignored in case of a console target and can be omitted.

Parameters

target_type_target_name (`str`) logging target

Return `None`

Throws *DevFailed* from device

New in PyTango 7.0.0

adm_name (*self*) → `str`

Return the name of the corresponding administrator device. This is useful if you need to send an administration command to the device server, e.g restart it

New in PyTango 3.0.4

alias (*self*) → `str`

Return the device alias if one is defined. Otherwise, throws exception.

Return (`str`) device alias

attribute_history (*self*, *attr_name*, *depth*, *extract_as=ExtractAs.Numpy*) → `sequence<DeviceAttributeHistory>`

Retrieve attribute history from the attribute polling buffer. See chapter on Advanced Feature for all details regarding polling

Parameters

attr_name (`str`) Attribute name.

depth (`int`) The wanted history depth.

extract_as (`ExtractAs`)

Return This method returns a vector of `DeviceAttributeHistory` types.

Throws *NonSupportedFeature*, *ConnectionFailed*,
CommunicationFailed, *DevFailed* from device

attribute_list_query (*self*) → sequence<AttributeInfo>

Query the device for info on all attributes. This method returns a sequence of tango.AttributeInfo.

Parameters None

Return (sequence<*AttributeInfo*>) containing the attributes configuration

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device

attribute_list_query_ex (*self*) → sequence<AttributeInfoEx>

Query the device for info on all attributes. This method returns a sequence of tango.AttributeInfoEx.

Parameters None

Return (sequence<*AttributeInfoEx*>) containing the attributes configuration

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device

attribute_query (*self*, *attr_name*) → AttributeInfoEx

Query the device for information about a single attribute.

Parameters

attr_name (*str*) the attribute name

Return (*AttributeInfoEx*) containing the attribute configuration

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device

black_box (*self*, *n*) → sequence<str>

Get the last commands executed on the device server

Parameters

n *n* number of commands to get

Return (sequence<*str*>) sequence of strings containing the date, time, command and from which client computer the command was executed

Example

```
print(black_box(4))
```

cancel_all_polling_asynch_request (*self*) → None

Cancel all running asynchronous request

This is a client side call. Obviously, the calls cannot be aborted while it is running in the device.

Parameters None

Return None

New in PyTango 7.0.0

cancel_asynch_request (*self*, *id*) → None

Cancel a running asynchronous request

This is a client side call. Obviously, the call cannot be aborted while it is running in the device.

Parameters

id The asynchronous call identifier

Return None

New in PyTango 7.0.0

command_history (*self*, *cmd_name*, *depth*) → sequence<DeviceDataHistory>

Retrieve command history from the command polling buffer. See chapter on Advanced Feature for all details regarding polling

Parameters

cmd_name (*str*) Command name.

depth (*int*) The wanted history depth.

Return This method returns a vector of DeviceDataHistory types.

Throws *NonSupportedFeature*, *ConnectionFailed*,
CommunicationFailed, *DevFailed* from device

command_inout (*self*, *cmd_name*, *cmd_param*=None, *green_mode*=None, *wait*=True, *timeout*=None) → any

Execute a command on a device.

Parameters

cmd_name (*str*) Command name.

cmd_param (*any*) It should be a value of the type expected by the command or a DeviceData object with this value inserted. It can be omitted if the command should not get any argument.

green_mode (*GreenMode*) Defaults to the current DeviceProxy GreenMode. (see *get_green_mode()* and *set_green_mode()*).

wait (*bool*) whether or not to wait for result. If *green_mode* is *Synchronous*, this parameter is ignored as it always waits for the result. Ignored when *green_mode* is *Synchronous* (always waits).

timeout (*float*) The number of seconds to wait for the result. If None, then there is no limit on the wait time. Ignored when *green_mode* is *Synchronous* or *wait* is False.

Return The result of the command. The type depends on the command. It may be None.

Throws *ConnectionFailed*, *CommunicationFailed*,
DeviceUnlocked, *DevFailed* from device *TimeoutError* (*green_mode* == *Futures*) If the future didn't finish executing before the given timeout. *Timeout* (*green_mode* == *Gevent*) If the async result didn't finish executing before the given timeout.

New in version 8.1.0: *green_mode* parameter. *wait* parameter. *timeout* parameter.

`command_inout_async(self, cmd_name) → id`

`command_inout_async(self, cmd_name, cmd_param) -> id`

`command_inout_async(self, cmd_name, cmd_param, forget) -> id`

Execute asynchronously (polling model) a command on a device

Parameters

cmd_name (`str`) Command name.

cmd_param (`any`) It should be a value of the type expected by the command or a `DeviceData` object with this value inserted. It can be omitted if the command should not get any argument. If the command should get no argument and you want to set the 'forget' param, use `None` for `cmd_param`.

forget (`bool`) If this flag is set to true, this means that the client does not care at all about the server answer and will even not try to get it. Default value is `False`. Please, note that device re-connection will not take place (in case it is needed) if the fire and forget mode is used. Therefore, an application using only fire and forget requests is not able to automatically re-connect to device.

Return (`int`) This call returns an asynchronous call identifier which is needed to get the command result (see `command_inout_reply`)

Throws `ConnectionFailed`, `TypeError`, anything thrown by `command_query`

`command_inout_async(self, cmd_name, callback) -> None`

`command_inout_async(self, cmd_name, cmd_param, callback) -> None`

Execute asynchronously (callback model) a command on a device.

Parameters

cmd_name (`str`) Command name.

cmd_param (`any`) It should be a value of the type expected by the command or a `DeviceData` object with this value inserted. It can be omitted if the command should not get any argument.

callback Any callable object (function, lambda...) or any object with a method named "cmd_ended".

Return `None`

Throws `ConnectionFailed`, `TypeError`, anything thrown by `command_query`

Important: by default, TANGO is initialized with the **polling** model. If you want to use the **push** model (the one with the `callback` parameter), you need to change the global TANGO model to `PUSH_CALLBACK`. You can do this with the `tango.class: `ApiUtil().set_async_cb_sub_model``

`command_inout_raw(self, cmd_name, cmd_param=None) → DeviceData`

Execute a command on a device.

Parameters

cmd_name (`str`) Command name.

cmd_param (any) It should be a value of the type expected by the command or a DeviceData object with this value inserted. It can be omitted if the command should not get any argument.

Return A DeviceData object.

Throws *ConnectionFailed*, *CommunicationFailed*, *DeviceUnlocked*, *DevFailed* from device

command_inout_reply (*self*, *id*) → DeviceData

Check if the answer of an asynchronous `command_inout` is arrived (polling model). If the reply is arrived and if it is a valid reply, it is returned to the caller in a DeviceData object. If the reply is an exception, it is re-thrown by this call. An exception is also thrown in case of the reply is not yet arrived.

Parameters

id (int) Asynchronous call identifier.

Return (*DeviceData*)

Throws *AsynCall*, *AsynReplyNotArrived*, *CommunicationFailed*, *DevFailed* from device

`command_inout_reply(self, id, timeout) -> DeviceData`

Check if the answer of an asynchronous `command_inout` is arrived (polling model). `id` is the asynchronous call identifier. If the reply is arrived and if it is a valid reply, it is returned to the caller in a *DeviceData* object. If the reply is an exception, it is re-thrown by this call. If the reply is not yet arrived, the call will wait (blocking the process) for the time specified in `timeout`. If after `timeout` milliseconds, the reply is still not there, an exception is thrown. If `timeout` is set to 0, the call waits until the reply arrived.

Parameters

id (int) Asynchronous call identifier.

timeout (int)

Return (*DeviceData*)

Throws *AsynCall*, *AsynReplyNotArrived*, *CommunicationFailed*, *DevFailed* from device

command_inout_reply_raw (*self*, *id*, *timeout*) → DeviceData

Check if the answer of an asynchronous `command_inout` is arrived (polling model). `id` is the asynchronous call identifier. If the reply is arrived and if it is a valid reply, it is returned to the caller in a DeviceData object. If the reply is an exception, it is re-thrown by this call. If the reply is not yet arrived, the call will wait (blocking the process) for the time specified in `timeout`. If after `timeout` milliseconds, the reply is still not there, an exception is thrown. If `timeout` is set to 0, the call waits until the reply arrived.

Parameters

id (int) Asynchronous call identifier.

timeout (int)

Return (*DeviceData*)

Throws *AsynCall*, *AsynReplyNotArrived*, *CommunicationFailed*, *DevFailed* from device

command_list_query (*self*) → sequence<CommandInfo>

Query the device for information on all commands.

Parameters None

Return (*CommandInfoList*) Sequence of *CommandInfo* objects

command_query (*self*, *command*) → *CommandInfo*

Query the device for information about a single command.

Parameters

command (*str*) command name

Return (*CommandInfo*) object

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device

Example

```
com_info = dev.command_query("DevString")
print(com_info.cmd_name)
print(com_info.cmd_tag)
print(com_info.in_type)
print(com_info.out_type)
print(com_info.in_type_desc)
print(com_info.out_type_desc)
print(com_info.disp_level)
```

See *CommandInfo* documentation string form more detail

connect (*self*, *corba_name*) → *None*

Creates a connection to a TANGO device using it's stringified CORBA reference i.e. IOR or corbaloc.

Parameters

corba_name (*str*) Name of the CORBA object

Return *None*

New in PyTango 7.0.0

delete_property (*self*, *value*)

Delete a the given of properties for this device. This method accepts the following types as value parameter:

1. string [in] - single property to be deleted
2. tango.DbDatum [in] - single property data to be deleted
3. tango.DbData [in] - several property data to be deleted
4. sequence<string> [in]- several property data to be deleted
5. sequence<DbDatum> [in] - several property data to be deleted
6. dict<str, obj> [in] - keys are property names to be deleted (values are ignored)

7. dict<str, DbDatum> [in] - several DbDatum.name are property names to be deleted (keys are ignored)

Parameters

value can be one of the following:

1. string [in] - single property data to be deleted
2. tango.DbDatum [in] - single property data to be deleted
3. tango.DbData [in] - several property data to be deleted
4. sequence<string> [in]- several property data to be deleted
5. sequence<DbDatum> [in] - several property data to be deleted
6. dict<str, obj> [in] - keys are property names to be deleted (values are ignored)
7. dict<str, DbDatum> [in] - several DbDatum.name are property names to be deleted (keys are ignored)

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError), TypeError

description (*self*) → str

Get device description.

Parameters None

Return (str) describing the device

dev_name (*self*) → str

Return the device name as it is stored locally

Parameters None

Return (str)

event_queue_size (*self*, *event_id*) → int

Returns the number of stored events in the event reception buffer. After every call to DeviceProxy.get_events(), the event queue size is 0. During event subscription the client must have chosen the 'pull model' for this event. event_id is the event identifier returned by the DeviceProxy.subscribe_event() method.

Parameters

event_id (int) event identifier

Return an integer with the queue size

Throws *EventSystemFailed*

New in PyTango 7.0.0

get_access_control (*self*) → AccessControlType

Returns the current access control type

Parameters None

Return (*AccessControlType*) The current access control type

New in PyTango 7.0.0

get_access_right (*self*) → *AccessControlType*

Returns the current access control type

Parameters None

Return (*AccessControlType*) The current access control type

New in PyTango 8.0.0

get_async_replies (*self*, *call_timeout*) → *None*

Try to obtain data returned by a command asynchronously requested. This method blocks for the specified timeout if the reply is not yet arrived. This method fires callback when the reply arrived. If the timeout is set to 0, the call waits indefinitely for the reply

Parameters

call_timeout (*int*) timeout in miliseconds

Return None

New in PyTango 7.0.0

get_attribute_config (*self*, *name*) → *AttributeInfoEx*

Return the attribute configuration for a single attribute.

Parameters

name (*str*) attribute name

Return (*AttributeInfoEx*) Object containing the attribute information

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device

Deprecated: use `get_attribute_config_ex` instead

get_attribute_config (*self*, *names*) → *AttributeInfoList*

Return the attribute configuration for the list of specified attributes. To get all the attributes pass a sequence containing the constant `tango::class::constants.AllAttr`

Parameters

names (sequence<*str*>) attribute names

Return (*AttributeInfoList*) Object containing the attributes information

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device, *TypeError*

Deprecated: use `get_attribute_config_ex` instead

get_attribute_config_ex (*self*, *name*) → *AttributeInfoListEx* :

Return the extended attribute configuration for a single attribute.

Parameters

name (*str*) attribute name

Return (*AttributeInfoEx*) Object containing the attribute information

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device

`get_attribute_config(self, names) -> AttributeInfoListEx :`

Return the extended attribute configuration for the list of specified attributes. To get all the attributes pass a sequence containing the constant `tango::class::constants.AllAttr`

Parameters

names (sequence<str>) attribute names

Return (*AttributeInfoList*) Object containing the attributes information

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device, *TypeError*

`get_attribute_list(self) -> sequence<str>`

Return the names of all attributes implemented for this device.

Parameters None

Return sequence<str>

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device

`get_attribute_poll_period(self, attr_name) -> int`

Return the attribute polling period.

Parameters

attr_name (str) attribute name

Return polling period in milliseconds

`get_command_config(self) -> CommandInfoList`

Return the command configuration for all commands.

Return (*CommandInfoList*) Object containing the commands information

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device, *TypeError*

`get_command_config(self, name) -> CommandInfo`

Return the command configuration for a single command.

Parameters

name (str) command name

Return (*CommandInfo*) Object containing the command information

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device, *TypeError*

`get_command_config(self, names) -> CommandInfoList`

Return the command configuration for the list of specified commands.

Parameters

names (sequence<str>) command names

Return (CommandInfoList) Object containing the commands information

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device, *TypeError*

get_command_list (*self*) → sequence<str>

Return the names of all commands implemented for this device.

Parameters None

Return sequence<str>

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device

get_command_poll_period (*self*, *cmd_name*) → int

Return the command polling period.

Parameters

cmd_name (str) command name

Return polling period in milliseconds

get_db_host (*self*) → str

Returns a string with the database host.

Parameters None

Return (str)

New in PyTango 7.0.0

get_db_port (*self*) → str

Returns a string with the database port.

Parameters None

Return (str)

New in PyTango 7.0.0

get_db_port_num (*self*) → int

Returns an integer with the database port.

Parameters None

Return (int)

New in PyTango 7.0.0

get_dev_host (*self*) → str

Returns the current host

Parameters None

Return (`str`) the current host

New in PyTango 7.2.0

get_dev_port (*self*) → `str`

Returns the current port

Parameters None

Return (`str`) the current port

New in PyTango 7.2.0

get_device_db (*self*) → Database

Returns the internal database reference

Parameters None

Return (`Database`) object

New in PyTango 7.0.0

get_events (*event_id*, *callback=None*, *extract_as=Numpy*) → `None`

The method extracts all waiting events from the event reception buffer.

If *callback* is not `None`, it is executed for every event. During event subscription the client must have chosen the pull model for this event. The callback will receive a parameter of type `EventData`, `AttrConfEventData` or `DataReadyEventData` depending on the type of the event (*event_type* parameter of `subscribe_event`).

If *callback* is `None`, the method extracts all waiting events from the event reception buffer. The returned `event_list` is a vector of `EventData`, `AttrConfEventData` or `DataReadyEventData` pointers, just the same data the callback would have received.

Parameters

event_id (`int`) is the event identifier returned by the `DeviceProxy.subscribe_event()` method.

callback (`callable`) Any callable object or any object with a "push_event" method.

extract_as (`ExtractAs`)

Return `None`

Throws `EventSystemFailed`, `TypeError`, `ValueError`

See Also `subscribe_event`

New in PyTango 7.0.0

get_fqdn (*self*) → `str`

Returns the fully qualified domain name

Parameters None

Return (`str`) the fully qualified domain name

New in PyTango 7.2.0

get_from_env_var (*self*) → `bool`

Returns True if determined by environment variable or False otherwise

Parameters None

Return (`bool`)

New in PyTango 7.0.0

get_green_mode ()

Returns the green mode in use by this DeviceProxy.

Returns the green mode in use by this DeviceProxy.

Return type *GreenMode*

See also:

tango.get_green_mode() *tango.set_green_mode()*

New in PyTango 8.1.0

get_idl_version (*self*) → `int`

Get the version of the Tango Device interface implemented by the device

Parameters None

Return (`int`)

get_last_event_date (*self*, *event_id*) → `TimeVal`

Returns the arrival time of the last event stored in the event reception buffer. After every call to `DeviceProxy.get_events()`, the event reception buffer is empty. In this case an exception will be returned. During event subscription the client must have chosen the 'pull model' for this event. *event_id* is the event identifier returned by the `DeviceProxy.subscribe_event()` method.

Parameters

event_id (`int`) event identifier

Return (*tango.TimeVal*) representing the arrival time

Throws *EventSystemFailed*

New in PyTango 7.0.0

get_locker (*self*, *lockinfo*) → `bool`

If the device is locked, this method returns True and sets some locker process information in the structure passed as argument. If the device is not locked, the method returns False.

Parameters

lockinfo [out] (`tango.LockInfo`) object that will be filled with lock information

Return (`bool`) True if the device is locked by us. Otherwise, False

New in PyTango 7.0.0

get_logging_level (*self*) → `int`

Returns the current device's logging level, where:

- 0=OFF
- 1=FATAL
- 2=ERROR
- 3=WARNING

- 4=INFO
- 5=DEBUG

:Parameters:None :Return: (`int`) representing the current logging level

New in PyTango 7.0.0

get_logging_target (*self*) → sequence<str>

Returns a sequence of string containing the current device's logging targets. Each vector element has the following format: `target_type::target_name`. An empty sequence is returned if the device has no logging targets.

Parameters None

Return a sequence<str> with the logging targets

New in PyTango 7.0.0

get_pipe_config (*self*) → PipeInfoList

Return the pipe configuration for all pipes.

Return (`PipeInfoList`) Object containing the pipes information

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device, `TypeError`

`get_pipe_config(self, name) -> PipeInfo`

Return the pipe configuration for a single pipe.

Parameters

name (`str`) pipe name

Return (`PipeInfo`) Object containing the pipe information

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device, `TypeError`

`get_pipe_config(self, names) -> PipeInfoList`

Return the pipe configuration for the list of specified pipes. To get all the pipes pass a sequence containing the constant `tango::class::constants.AllPipe`

Parameters

names (sequence<str>) pipe names

Return (`PipeInfoList`) Object containing the pipes information

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device, `TypeError`

New in PyTango 9.2.0

get_property (*propname*, *value=None*) → tango.DbData

Get a (list) property(ies) for a device.

This method accepts the following types as `propname` parameter: 1. `string` [`in`] - single property data to be fetched 2. `sequence<string>` [`in`] - several property data to be fetched 3. `tango.DbDatum` [`in`] - single property data to be fetched 4. `tango.DbData` [`in,out`] - several property data to be fetched. 5. `sequence<DbDatum>` - several property data to be fetched

Note: for cases 3, 4 and 5 the 'value' parameter if given, is IGNORED.

If value is given it must be a tango.DbData that will be filled with the property values

Parameters

propname (any) property(ies) name(s)

value (DbData) (optional, default is None meaning that the method will create internally a tango.DbData and return it filled with the property values

Return (DbData) object containing the property(ies) value(s). If a tango.DbData is given as parameter, it returns the same object otherwise a new tango.DbData is returned

Throws *NonDbDevice*, *ConnectionFailed* (with database), *CommunicationFailed* (with database), *DevFailed* from database device

get_property_list (*self*, *filter*, *array=None*) → obj

Get the list of property names for the device. The parameter filter allows the user to filter the returned name list. The wildcard character is '*'. Only one wildcard character is allowed in the filter parameter.

Parameters

filter[in] (*str*) the filter wildcard

array[out] (sequence obj or None) (optional, default is None) an array to be filled with the property names. If None a new list will be created internally with the values.

Return the given array filled with the property names (or a new list if array is None)

Throws *NonDbDevice*, *WrongNameSyntax*, *ConnectionFailed* (with database), *CommunicationFailed* (with database), *DevFailed* from database device, *TypeError*

New in PyTango 7.0.0

get_source (*self*) → *DevSource*

Get the data source(device, polling buffer, polling buffer then device) used by command_inout or read_attribute methods

Parameters None

Return (*DevSource*)

Example

```
source = dev.get_source()
if source == DevSource.CACHE_DEV : ...
```

get_tango_lib_version (*self*) → *int*

Returns the Tango lib version number used by the remote device Otherwise, throws exception.

Return (*int*) The device Tango lib version as a 3 or 4 digits number. Possible return value are: 100,200,500,520,700,800,810,...

New in PyTango 8.1.0

get_timeout_millis (*self*) → *int*

Get the client side timeout in milliseconds

Parameters None

Return (*int*)

get_transparency_reconnection (*self*) → *bool*

Returns the device transparency reconnection flag.

Parameters None

Return (*bool*) True if transparency reconnection is set or False otherwise

import_info (*self*) → *DbDevImportInfo*

Query the device for import info from the database.

Parameters None

Return (*DbDevImportInfo*)

Example

```
dev_import = dev.import_info()
print(dev_import.name)
print(dev_import.exported)
print(dev_ior.ior)
print(dev_version.version)
```

All *DbDevImportInfo* fields are strings except for *exported* which is an integer"

info (*self*) → *DeviceInfo*

A method which returns information on the device

Parameters None

Return (*DeviceInfo*) object

Example

```
dev_info = dev.info()
print(dev_info.dev_class)
print(dev_info.server_id)
print(dev_info.server_host)
print(dev_info.server_version)
print(dev_info.doc_url)
print(dev_info.dev_type)
```

All *DeviceInfo* fields are strings **except for** the *server_version* which **is** an integer"

is_attribute_polled (*self*, *attr_name*) → *bool*

True if the attribute is polled.

Parameters

attr_name (*str*) attribute name

Return boolean value

is_command_polled (*self*, *cmd_name*) → bool

True if the command is polled.

Parameters

cmd_name (*str*) command name

Return boolean value

is_dbase_used (*self*) → bool

Returns if the database is being used

Parameters None

Return (*bool*) True if the database is being used

New in PyTango 7.2.0

is_event_queue_empty (*self*, *event_id*) → bool

Returns true when the event reception buffer is empty. During event subscription the client must have chosen the 'pull model' for this event. *event_id* is the event identifier returned by the DeviceProxy.subscribe_event() method.

Parameters

event_id (*int*) event identifier

Return (*bool*) True if queue is empty or False otherwise

Throws *EventSystemFailed*

New in PyTango 7.0.0

is_locked (*self*) → bool

Returns True if the device is locked. Otherwise, returns False.

Parameters None

Return (*bool*) True if the device is locked. Otherwise, False

New in PyTango 7.0.0

is_locked_by_me (*self*) → bool

Returns True if the device is locked by the caller. Otherwise, returns False (device not locked or locked by someone else)

Parameters None

Return (*bool*) True if the device is locked by us. Otherwise, False

New in PyTango 7.0.0

lock (*self*, (*int*)*lock_validity*) → None

Lock a device. The *lock_validity* is the time (in seconds) the lock is kept valid after the previous lock call. A default value of 10 seconds is provided and should be fine in most cases. In case it is necessary to change the lock validity, it's not possible to ask for a validity less than a minimum value set to 2 seconds. The library provided an automatic system to periodically re lock the device until an unlock call. No code is needed to start/stop this automatic re-locking system. The locking system is re-entrant. It is then allowed to call this method on a device already locked by the same process. The locking system has the following features:

- It is impossible to lock the database device or any device server process admin device
- Destroying a locked DeviceProxy unlocks the device
- Restarting a locked device keeps the lock
- It is impossible to restart a device locked by someone else
- Restarting a server breaks the lock

A locked device is protected against the following calls when executed by another client:

- `command_inout` call except for device state and status requested via `command` and for the set of commands defined as allowed following the definition of allowed command in the Tango control access schema.
- `write_attribute` call
- `write_read_attribute` call
- `set_attribute_config` call

Parameters

`lock_validity` (`int`) lock validity time in seconds (optional, default value is `tango.constants.DEFAULT_LOCK_VALIDITY`)

Return None

New in PyTango 7.0.0

locking_status (`self`) → `str`

This method returns a plain string describing the device locking status. This string can be:

- 'Device <device name> is not locked' in case the device is not locked
- 'Device <device name> is locked by CPP or Python client with PID <pid> from host <host name>' in case the device is locked by a CPP client
- 'Device <device name> is locked by JAVA client class <main class> from host <host name>' in case the device is locked by a JAVA client

Parameters None

Return a string representing the current locking status

New in PyTango 7.0.0

name (`self`) → `str`

Return the device name from the device itself.

pending_asynch_call (`self`) → `int`

Return number of device asynchronous pending requests"

New in PyTango 7.0.0

ping (`self`) → `int`

A method which sends a ping to the device

Parameters None

Return (`int`) time elapsed in microseconds

Throws `exception` if device is not alive

poll_attribute (*self*, *attr_name*, *period*) → None

Add an attribute to the list of polled attributes.

Parameters

attr_name (*str*) attribute name

period (*int*) polling period in milliseconds

Return None

poll_command (*self*, *cmd_name*, *period*) → None

Add a command to the list of polled commands.

Parameters

cmd_name (*str*) command name

period (*int*) polling period in milliseconds

Return None

polling_status (*self*) → sequence<str>

Return the device polling status.

Parameters None

Return (sequence<str>) One string for each polled command/attribute. Each string is multi-line string with:

- attribute/command name
- attribute/command polling period in milliseconds
- attribute/command polling ring buffer
- time needed for last attribute/command execution in milliseconds
- time since data in the ring buffer has not been updated
- delta time between the last records in the ring buffer
- exception parameters in case of the last execution failed

put_property (*self*, *value*) → None

Insert or update a list of properties for this device. This method accepts the following types as value parameter: 1. `tango.DbDatum` - single property data to be inserted 2. `tango.DbData` - several property data to be inserted 3. `sequence<DbDatum>` - several property data to be inserted 4. `dict<str, DbDatum>` - keys are property names and value has data to be inserted 5. `dict<str, seq<str>>` - keys are property names and value has data to be inserted 6. `dict<str, obj>` - keys are property names and `str(obj)` is property value

Parameters

value can be one of the following: 1. `tango.DbDatum` - single property data to be inserted 2. `tango.DbData` - several property data to be inserted 3. `sequence<DbDatum>` - several property data to be inserted 4. `dict<str, DbDatum>` - keys are property names and value has data to be inserted 5. `dict<str, seq<str>>` - keys are property names and value has data to be inserted 6. `dict<str, obj>` - keys are property names and `str(obj)` is property value

Return None

Throws *ConnectionFailed*, *CommunicationFailed* *DevFailed* from device (*DB_SQLError*)

read_attribute (*self*, *attr_name*, *extract_as=ExtractAs.Numpy*, *green_mode=None*, *wait=True*, *timeout=None*) → *DeviceAttribute*

Read a single attribute.

Parameters

attr_name (*str*) The name of the attribute to read.

extract_as (*ExtractAs*) Defaults to *numpy*.

green_mode (*GreenMode*) Defaults to the current *DeviceProxy GreenMode*. (see *get_green_mode()* and *set_green_mode()*).

wait (*bool*) whether or not to wait for result. If *green_mode* is *Synchronous*, this parameter is ignored as it always waits for the result. Ignored when *green_mode* is *Synchronous* (always waits).

timeout (*float*) The number of seconds to wait for the result. If *None*, then there is no limit on the wait time. Ignored when *green_mode* is *Synchronous* or *wait* is *False*.

Return (*DeviceAttribute*)

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device *TimeoutError* (*green_mode == Futures*) If the future didn't finish executing before the given timeout. *Timeout* (*green_mode == Gevent*) If the async result didn't finish executing before the given timeout.

Changed in version 7.1.4: For *DevEncoded* attributes, before it was returning a *DeviceAttribute.value* as a tuple (**format<str>**, **data<str>**) no matter what was the *extract_as* value was. Since 7.1.4, it returns a (**format<str>**, **data<buffer>**) unless *extract_as* is *String*, in which case it returns (**format<str>**, **data<str>**).

Changed in version 8.0.0: For *DevEncoded* attributes, now returns a *DeviceAttribute.value* as a tuple (**format<str>**, **data<bytes>**) unless *extract_as* is *String*, in which case it returns (**format<str>**, **data<str>**). Carefull, if using python >= 3 **data<str>** is decoded using default python *utf-8* encoding. This means that PyTango assumes tango DS was written encapsulating string into *utf-8* which is the default python encoding.

New in version 8.1.0: *green_mode* parameter. *wait* parameter. *timeout* parameter.

read_attribute_async (*self*, *attr_name*) → *int*
read_attribute_async (*self*, *attr_name*, *callback*) → *None*

Shortcut to *self.read_attributes_async([attr_name], cb)*

New in PyTango 7.0.0

read_attribute_reply (*self*, *id*, *extract_as*) → *int*
read_attribute_reply (*self*, *id*, *timeout*, *extract_as*) → *None*

Shortcut to *self.read_attributes_reply()[0]*

New in PyTango 7.0.0

read_attributes (*self*, *attr_names*, *extract_as=ExtractAs.Numpy*, *green_mode=None*, *wait=True*, *timeout=None*) → *sequence<DeviceAttribute>*

Read the list of specified attributes.

Parameters

attr_names (sequence<str>) A list of attributes to read.

extract_as (ExtractAs) Defaults to numpy.

green_mode (*GreenMode*) Defaults to the current DeviceProxy *GreenMode*. (see *get_green_mode()* and *set_green_mode()*).

wait (bool) whether or not to wait for result. If *green_mode* is *Synchronous*, this parameter is ignored as it always waits for the result. Ignored when *green_mode* is *Synchronous* (always waits).

timeout (float) The number of seconds to wait for the result. If None, then there is no limit on the wait time. Ignored when *green_mode* is *Synchronous* or *wait* is False.

Return (sequence<*DeviceAttribute*>)

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device *TimeoutError* (*green_mode* == *Futures*) If the future didn't finish executing before the given timeout. *Timeout* (*green_mode* == *Gevent*) If the async result didn't finish executing before the given timeout.

New in version 8.1.0: *green_mode* parameter. *wait* parameter. *timeout* parameter.

read_attributes_async (*self*, *attr_names*) → int

Read asynchronously (polling model) the list of specified attributes.

Parameters

attr_names (sequence<str>) A list of attributes to read. It should be a *StdStringVector* or a sequence of str.

Return an asynchronous call identifier which is needed to get attributes value.

Throws *ConnectionFailed*

New in PyTango 7.0.0

read_attributes_async (*self*, *attr_names*, *callback*, *extract_as=Numpy*) -> None

Read asynchronously (push model) an attribute list.

Parameters

attr_names (sequence<str>) A list of attributes to read. See *read_attributes*.

callback (callable) This callback object should be an instance of a user class with an *attr_read()* method. It can also be any callable object.

extract_as (ExtractAs) Defaults to numpy.

Return None

Throws *ConnectionFailed*

New in PyTango 7.0.0

Important: by default, TANGO is initialized with the **polling** model. If you want to use the **push** model (the one with the callback parameter), you need to change the global TANGO model to PUSH_CALLBACK. You can do this with the `tango.ApiUtil.set_asynch_cb_sub_model()`

read_attributes_reply (*self*, *id*, *extract_as*=*ExtractAs.Numpy*) → *DeviceAttribute*

Check if the answer of an asynchronous read_attribute is arrived (polling model).

Parameters

id (*int*) is the asynchronous call identifier.

extract_as (*ExtractAs*)

Return If the reply is arrived and if it is a valid reply, it is returned to the caller in a list of *DeviceAttribute*. If the reply is an exception, it is re-thrown by this call. An exception is also thrown in case of the reply is not yet arrived.

Throws *AsynCall*, *AsynReplyNotArrived*, *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device

New in PyTango 7.0.0

read_attributes_reply (*self*, *id*, *timeout*, *extract_as*=*ExtractAs.Numpy*) → *DeviceAttribute*

Check if the answer of an asynchronous read_attributes is arrived (polling model).

Parameters

id (*int*) is the asynchronous call identifier.

timeout (*int*)

extract_as (*ExtractAs*)

Return If the reply is arrived and if it is a valid reply, it is returned to the caller in a list of *DeviceAttribute*. If the reply is an exception, it is re-thrown by this call. If the reply is not yet arrived, the call will wait (blocking the process) for the time specified in *timeout*. If after *timeout* milliseconds, the reply is still not there, an exception is thrown. If *timeout* is set to 0, the call waits until the reply arrived.

Throws *AsynCall*, *AsynReplyNotArrived*, *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device

New in PyTango 7.0.0

read_pipe (*self*, *pipe_name*, *extract_as*=*ExtractAs.Numpy*, *green_mode*=*None*, *wait*=*True*, *timeout*=*None*) → *tuple*

Read a single pipe. The result is a *blob*: a tuple with two elements: blob name (string) and blob data (sequence). The blob data consists of a sequence where each element is a dictionary with the following keys:

- name: blob element name
- dtype: tango data type
- value: blob element data (str for *DevString*, etc)

In case *dtype* is *DevPipeBlob*, value is again a *blob*.

Parameters

pipe_name (*str*) The name of the pipe to read.

extract_as (*ExtractAs*) Defaults to *numpy*.

green_mode (*GreenMode*) Defaults to the current *DeviceProxy* *GreenMode*. (see *get_green_mode()* and *set_green_mode()*).

wait (*bool*) whether or not to wait for result. If *green_mode* is *Synchronous*, this parameter is ignored as it always waits for the result. Ignored when *green_mode* is *Synchronous* (always waits).

timeout (*float*) The number of seconds to wait for the result. If *None*, then there is no limit on the wait time. Ignored when *green_mode* is *Synchronous* or *wait* is *False*.

Return *tuple*<*str*, *sequence*>

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device *TimeoutError* (*green_mode* == *Futures*) If the future didn't finish executing before the given timeout. *Timeout* (*green_mode* == *Gevent*) If the async result didn't finish executing before the given timeout.

New in PyTango 9.2.0

reconnect (*self*, *db_used*) → *None*

Reconnect to a CORBA object.

Parameters

db_used (*bool*) Use thatabase

Return *None*

New in PyTango 7.0.0

remove_logging_target (*self*, *target_type_target_name*) → *None*

Removes a logging target from the device's target list.

The *target_type_target_name* input parameter must follow the format: *target_type::target_name*. Supported target types are: *console*, *file* and *device*. For a device target, the *target_name* part of the *target_type_target_name* parameter must contain the name of a log consumer device (as defined in). For a file target, *target_name* is the full path to the file to remove. If omitted, the default log file is removed. Finally, the *target_name* part of the *target_type_target_name* input parameter is ignored in case of a console target and can be omitted. If *target_name* is set to ***, all targets of the specified *target_type* are removed.

Parameters

target_type_target_name (*str*) logging target

Return *None*

New in PyTango 7.0.0

set_access_control (*self*, *acc*) → *None*

Sets the current access control type

Parameters

acc (*AccessControlType*) the type of access control to set

Return *None*

New in PyTango 7.0.0

set_attribute_config (*self*, *attr_info*) → None

Change the attribute configuration for the specified attribute

Parameters

attr_info (*AttributeInfo*) attribute information

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device, *TypeError*

set_attribute_config(self, attr_info_ex) -> None

Change the extended attribute configuration for the specified attribute

Parameters

attr_info_ex (*AttributeInfoEx*) extended attribute information

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device, *TypeError*

set_attribute_config(self, attr_info) -> None

Change the attributes configuration for the specified attributes

Parameters

attr_info (sequence<*AttributeInfo*>) attributes information

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device, *TypeError*

set_attribute_config(self, attr_info_ex) -> None

Change the extended attributes configuration for the specified attributes

Parameters

attr_info_ex (sequence<*AttributeInfoListEx*>) extended attributes information

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device, *TypeError*

set_green_mode (*green_mode=*None)

Sets the green mode to be used by this DeviceProxy Setting it to None means use the global PyTango green mode (see *tango.get_green_mode()*).

Parameters **green_mode** (*GreenMode*) – the new green mode

New in PyTango 8.1.0

set_logging_level (*self*, (*int*)*level*) → None

Changes the device's logging level, where:

- 0=OFF

- 1=FATAL
- 2=ERROR
- 3=WARNING
- 4=INFO
- 5=DEBUG

Parameters

level (`int`) logging level

Return None

New in PyTango 7.0.0

set_pipe_config (*self*, *pipe_info*) → None

Change the pipe configuration for the specified pipe

Parameters

pipe_info (`PipeInfo`) pipe information

Return None

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed`
from device, `TypeError`

`set_pipe_config(self, pipe_info) -> None`

Change the pipes configuration for the specified pipes

Parameters

pipe_info (`sequence<PipeInfo>`) pipes information

Return None

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed`
from device, `TypeError`

set_source (*self*, *source*) → None

Set the data source(device, polling buffer, polling buffer then device) for `command_inout` and `read_attribute` methods.

Parameters

source (`DevSource`) constant.

Return None

Example

```
dev.set_source(DevSource.CACHE_DEV)
```

set_timeout_millis (*self*, *timeout*) → None

Set client side timeout for device in milliseconds. Any method which takes longer than this time to execute will throw an exception

Parameters

timeout integer value of timeout in milliseconds

Return None

Example

```
dev.set_timeout_millis(1000)
```

set_transparency_reconnection (*self*, *yesno*) → *None*

Set the device transparency reconnection flag

Parameters " - val : (bool) True to set transparency reconnection " or False otherwise**Return** *None***state** (*self*) → *DevState*

A method which returns the state of the device.

Parameters *None***Return** (*DevState*) constant**Example**

```
dev_st = dev.state()
if dev_st == DevState.ON : ...
```

status (*self*) → *str*

A method which returns the status of the device as a string.

Parameters *None***Return** (*str*) describing the device status**stop_poll_attribute** (*self*, *attr_name*) → *None*

Remove an attribute from the list of polled attributes.

Parameters**attr_name** (*str*) attribute name**Return** *None***stop_poll_command** (*self*, *cmd_name*) → *None*

Remove a command from the list of polled commands.

Parameters**cmd_name** (*str*) command name**Return** *None***subscribe_event** (*event_type*, *cb*, *stateless=False*, *green_mode=None*) → *int*

The client call to subscribe for event reception in the push model. The client implements a callback method which is triggered when the event is received. This method is currently used device interface change events only.

Parameters

event_type (*EventType*) Is the event reason and must be on the enumerated values: * EventType.INTERFACE_CHANGE_EVENT

callback (*callable*) Is any callable object or an object with a callable “push_event” method.

stateless (*bool*) When the this flag is set to false, an exception will be thrown when the event subscription encounters a problem. With the stateless flag set to true, the event subscription will always succeed, even if the corresponding device server is not running. The keep alive thread will try every 10 seconds to subscribe for the specified event. At every subscription retry, a callback is executed which contains the corresponding exception

green_mode the corresponding green mode (default is GreenMode.Synchronous)

Return An event id which has to be specified when unsubscribing from this event.

Throws *EventSystemFailed*, *TypeError*

subscribe_event(self, attr_name, event, callback, filters=[], stateless=False, extract_as=Numpy, green_mode=None) -> int

The client call to subscribe for event reception in the push model. The client implements a `callback` method which is triggered when the event is received. Filtering is done based on the reason specified and the event type. For example when reading the state and the reason specified is “change” the event will be fired only when the state changes. Events consist of an attribute name and the event reason. A standard set of reasons are implemented by the system, additional device specific reasons can be implemented by device servers programmers.

Parameters

attr_name (*str*) The device attribute name which will be sent as an event e.g. “current”.

event_type (*EventType*) Is the event reason and must be on the enumerated values: * EventType.CHANGE_EVENT * EventType.PERIODIC_EVENT * EventType.ARCHIVE_EVENT * EventType.ATTR_CONF_EVENT * EventType.DATA_READY_EVENT * EventType.USER_EVENT

callback (*callable*) Is any callable object or an object with a callable “push_event” method.

filters (sequence<*str*>) A variable list of name,value pairs which define additional filters for events.

stateless (*bool*) When the this flag is set to false, an exception will be thrown when the event subscription encounters a problem. With the stateless flag set to true, the event subscription will always succeed, even if the corresponding device server is not running. The keep alive thread will try every 10 seconds to subscribe for the specified event. At every subscription retry, a callback is executed which contains the corresponding exception

extract_as (*ExtractAs*)

green_mode the corresponding green mode (default is Green-Mode.Synchronous)

Return An event id which has to be specified when unsubscribing from this event.

Throws *EventSystemFailed*, *TypeError*

`subscribe_event(self, attr_name, event, queue_size, filters=[], stateless=False, green_mode=None) -> int`

The client call to subscribe for event reception in the pull model. Instead of a `callback` method the client has to specify the size of the event reception buffer.

The event reception buffer is implemented as a round robin buffer. This way the client can set-up different ways to receive events:

- Event reception buffer size = 1 : The client is interested only in the value of the last event received. All other events that have been received since the last reading are discarded.
- Event reception buffer size > 1 : The client has chosen to keep an event history of a given size. When more events arrive since the last reading, older events will be discarded.
- Event reception buffer size = ALL_EVENTS : The client buffers all received events. The buffer size is unlimited and only restricted by the available memory for the client.

All other parameters are similar to the descriptions given in the other `subscribe_event()` version.

unlock (*self*, (*bool*)*force*) → *None*

Unlock a device. If used, the method argument provides a back door on the locking system. If this argument is set to true, the device will be unlocked even if the caller is not the locker. This feature is provided for administration purpose and should be used very carefully. If this feature is used, the locker will receive a *DeviceUnlocked* during the next call which is normally protected by the locking Tango system.

Parameters

force (*bool*) force unlocking even if we are not the locker (optional, default value is False)

Return *None*

New in PyTango 7.0.0

unsubscribe_event (*self*, *event_id*) → *None*

Unsubscribes a client from receiving the event specified by *event_id*.

Parameters

event_id (*int*) is the event identifier returned by the *DeviceProxy::subscribe_event()*. Unlike in *TangoC++* we check that the *event_id* has been subscribed in this *DeviceProxy*.

Return *None*

Throws *EventSystemFailed*, *KeyError*

write_attribute (*self*, *attr_name*, *value*, *green_mode=None*, *wait=True*, *timeout=None*) →

None
write_attribute (*self*, *attr_info*, *value*, *green_mode=None*, *wait=True*, *timeout=None*) -> *None*

Write a single attribute.

Parameters

attr_name (*str*) The name of the attribute to write.

attr_info (*AttributeInfo*)

value The value. For non SCALAR attributes it may be any sequence of sequences.

green_mode (*GreenMode*) Defaults to the current DeviceProxy GreenMode. (see *get_green_mode()* and *set_green_mode()*).

wait (*bool*) whether or not to wait for result. If *green_mode* is *Synchronous*, this parameter is ignored as it always waits for the result. Ignored when *green_mode* is *Synchronous* (always waits).

timeout (*float*) The number of seconds to wait for the result. If *None*, then there is no limit on the wait time. Ignored when *green_mode* is *Synchronous* or *wait* is *False*.

Throws *ConnectionFailed*, *CommunicationFailed*, *DeviceUnlocked*, *DevFailed* from device *TimeoutError* (*green_mode == Futures*) If the future didn't finish executing before the given timeout. *Timeout* (*green_mode == Gevent*) If the *async* result didn't finish executing before the given timeout.

New in version 8.1.0: *green_mode* parameter. *wait* parameter. *timeout* parameter.

write_attribute_async (*attr_name, value, cb=None*)

`write_attributes_async(self, values) -> int`
`write_attributes_async(self, values, callback) -> None`

Shortcut to `self.write_attributes_async([attr_name, value], cb)`

New in PyTango 7.0.0

write_attribute_reply (*self, id*) → *None*

Check if the answer of an asynchronous `write_attribute` is arrived (polling model). If the reply is arrived and if it is a valid reply, the call returned. If the reply is an exception, it is re-thrown by this call. An exception is also thrown in case of the reply is not yet arrived.

Parameters

id (*int*) the asynchronous call identifier.

Return *None*

Throws *AsyncCall*, *AsyncReplyNotArrived*, *CommunicationFailed*, *DevFailed* from device.

New in PyTango 7.0.0

write_attribute_reply (*self, id, timeout*) -> *None*

Check if the answer of an asynchronous `write_attribute` is arrived (polling model). *id* is the asynchronous call identifier. If the reply is arrived and if it is a valid reply, the call returned. If the reply is an exception, it is re-thrown by this call. If the reply is not yet arrived, the call will wait (blocking the process) for the time specified in *timeout*. If after *timeout* milliseconds, the reply is still not there, an exception is thrown. If *timeout* is set to 0, the call waits until the reply arrived.

Parameters

id (*int*) the asynchronous call identifier.

timeout (*int*) the timeout

Return None

Throws *AsyncCall*, *AsyncReplyNotArrived*,
CommunicationFailed, *DevFailed* from device.

New in PyTango 7.0.0

write_attributes (*self*, *name_val*, *green_mode=None*, *wait=True*, *timeout=None*) → None

Write the specified attributes.

Parameters

name_val A list of pairs (attr_name, value). See write_attribute

green_mode (*GreenMode*) Defaults to the current DeviceProxy GreenMode. (see *get_green_mode()* and *set_green_mode()*).

wait (*bool*) whether or not to wait for result. If green_mode is *Synchronous*, this parameter is ignored as it always waits for the result. Ignored when green_mode is *Synchronous* (always waits).

timeout (*float*) The number of seconds to wait for the result. If None, then there is no limit on the wait time. Ignored when green_mode is *Synchronous* or wait is False.

Throws *ConnectionFailed*, *CommunicationFailed*,
DeviceUnlocked, *DevFailed* or *NamedDevFailedList* from device
TimeoutError (green_mode == *Futures*) If the future didn't finish executing before the given timeout. *Timeout* (green_mode == *Event*) If the async result didn't finish executing before the given timeout.

New in version 8.1.0: green_mode parameter. wait parameter. timeout parameter.

write_attributes_async (*self*, *values*) → *int*

Write asynchronously (polling model) the specified attributes.

Parameters

values (*any*) See write_attributes.

Return An asynchronous call identifier which is needed to get the server reply

Throws *ConnectionFailed*

New in PyTango 7.0.0

write_attributes_async (*self*, *values*, *callback*) → None

Write asynchronously (callback model) a single attribute.

Parameters

values (*any*) See write_attributes.

callback (callable) This callback object should be an instance of a user class with an `attr_written()` method . It can also be any callable object.

Return None

Throws *ConnectionFailed*

New in PyTango 7.0.0

Important: by default, TANGO is initialized with the **polling** model. If you want to use the **push** model (the one with the callback parameter), you need to change the global TANGO model to PUSH_CALLBACK. You can do this with the `tango.ApiUtil.set_asynch_cb_sub_model()`

write_attributes_reply (*self, id*) → None

Check if the answer of an asynchronous `write_attributes` is arrived (polling model). If the reply is arrived and if it is a valid reply, the call returned. If the reply is an exception, it is re-thrown by this call. An exception is also thrown in case of the reply is not yet arrived.

Parameters

id (*int*) the asynchronous call identifier.

Return None

Throws *AsyncCall*, *AsyncReplyNotArrived*, *CommunicationFailed*, *DevFailed* from device.

New in PyTango 7.0.0

write_attributes_reply (*self, id, timeout*) -> None

Check if the answer of an asynchronous `write_attributes` is arrived (polling model). `id` is the asynchronous call identifier. If the reply is arrived and if it is a valid reply, the call returned. If the reply is an exception, it is re-thrown by this call. If the reply is not yet arrived, the call will wait (blocking the process) for the time specified in `timeout`. If after `timeout` milliseconds, the reply is still not there, an exception is thrown. If `timeout` is set to 0, the call waits until the reply arrived.

Parameters

id (*int*) the asynchronous call identifier.

timeout (*int*) the timeout

Return None

Throws *AsyncCall*, *AsyncReplyNotArrived*, *CommunicationFailed*, *DevFailed* from device.

New in PyTango 7.0.0

write_pipe (*self, blob, green_mode=None, wait=True, timeout=None*)

Write a *blob* to a single pipe. The *blob* comprises: a tuple with two elements: blob name (string) and blob data (sequence). The blob data consists of a sequence where each element is a dictionary with the following keys:

- name: blob element name
- dtype: tango data type

- value: blob element data (str for DevString, etc)

In case dtype is DevPipeBlob, value is also a *blob*.

Parameters

blob a tuple with two elements: blob name (string) and blob data (sequence).

green_mode (*GreenMode*) Defaults to the current DeviceProxy GreenMode. (see *get_green_mode()* and *set_green_mode()*).

wait (*bool*) whether or not to wait for result. If green_mode is *Synchronous*, this parameter is ignored as it always waits for the result. Ignored when green_mode is *Synchronous* (always waits).

timeout (*float*) The number of seconds to wait for the result. If None, then there is no limit on the wait time. Ignored when green_mode is *Synchronous* or wait is False.

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device *TimeoutError* (green_mode == *Futures*) If the future didn't finish executing before the given timeout. *Timeout* (green_mode == *Gevent*) If the async result didn't finish executing before the given timeout.

New in PyTango 9.2.1

write_read_attribute (*self*, *attr_name*, *value*, *extract_as=ExtractAs.Numpy*, *green_mode=None*, *wait=True*, *timeout=None*) → *DeviceAttribute*

Write then read a single attribute in a single network call. By default (serialisation by device), the execution of this call in the server can't be interrupted by other clients.

Parameters see *write_attribute(attr_name, value)*

Return A *tango.DeviceAttribute* object.

Throws *ConnectionFailed*, *CommunicationFailed*, *DeviceUnlocked*, *DevFailed* from device, *WrongData TimeoutError* (green_mode == *Futures*) If the future didn't finish executing before the given timeout. *Timeout* (green_mode == *Gevent*) If the async result didn't finish executing before the given timeout.

New in PyTango 7.0.0

New in version 8.1.0: *green_mode* parameter. *wait* parameter. *timeout* parameter.

write_read_attributes (*self*, *name_val*, *attr_names*, *extract_as=ExtractAs.Numpy*, *green_mode=None*, *wait=True*, *timeout=None*) → *DeviceAttribute*

Write then read attribute(s) in a single network call. By default (serialisation by device), the execution of this call in the server can't be interrupted by other clients. On the server side, attribute(s) are first written and if no exception has been thrown during the write phase, attributes will be read.

Parameters

name_val A list of pairs (*attr_name*, *value*). See *write_attribute*

attr_names (*sequence<str>*) A list of attributes to read.

extract_as (*ExtractAs*) Defaults to *numpy*.

green_mode (*GreenMode*) Defaults to the current DeviceProxy GreenMode. (see *get_green_mode()* and *set_green_mode()*).

wait (*bool*) whether or not to wait for result. If *green_mode* is *Synchronous*, this parameter is ignored as it always waits for the result. Ignored when *green_mode* is *Synchronous* (always waits).

timeout (*float*) The number of seconds to wait for the result. If *None*, then there is no limit on the wait time. Ignored when *green_mode* is *Synchronous* or *wait* is *False*.

Return (*sequence*<*DeviceAttribute*>)

Throws *ConnectionFailed*, *CommunicationFailed*, *DeviceUnlocked*, *DevFailed* from device, *WrongData* *TimeoutError* (*green_mode* == *Futures*) If the future didn't finish executing before the given timeout. *Timeout* (*green_mode* == *Gevent*) If the async result didn't finish executing before the given timeout.

New in PyTango 9.2.0

5.2.2 AttributeProxy

class `tango.AttributeProxy` (**args, **kwargs*)

AttributeProxy is the high level Tango object which provides the client with an easy-to-use interface to TANGO attributes.

To create an AttributeProxy, a complete attribute name must be set in the object constructor.

Example: `att = AttributeProxy("tango/tangotest/1/long_scalar")`

Note: PyTango implementation of AttributeProxy is in part a python reimplementaion of the AttributeProxy found on the C++ API.

delete_property (*self, value*) → *None*

Delete a the given of properties for this attribute. This method accepts the following types as value parameter:

1. *string* [*in*] - single property to be deleted
2. *tango.DbDatum* [*in*] - single property data to be deleted
3. *tango.DbData* [*in*] - several property data to be deleted
4. *sequence*<*string*> [*in*]- several property data to be deleted
5. *sequence*<*DbDatum*> [*in*] - several property data to be deleted
6. *dict*<*str, obj*> [*in*] - keys are property names to be deleted (values are ignored)
7. *dict*<*str, DbDatum*> [*in*] - several *DbDatum.name* are property names to be deleted (keys are ignored)

Parameters

value can be one of the following:

1. *string* [*in*] - single property data to be deleted
2. *tango.DbDatum* [*in*] - single property data to be deleted
3. *tango.DbData* [*in*] - several property data to be deleted
4. *sequence*<*string*> [*in*]- several property data to be deleted
5. *sequence*<*DbDatum*> [*in*] - several property data to be deleted

6. dict<str, obj> [in] - keys are property names to be deleted (values are ignored)
7. dict<str, DbDatum> [in] - several DbDatum.name are property names to be deleted (keys are ignored)

Return None

Throws *ConnectionFailed*, *CommunicationFailed* *DevFailed* from device (DB_SQLError), TypeError

event_queue_size (*args, **kws)

This method is a simple way to do: self.get_device_proxy().event_queue_size(...)

For convenience, here is the documentation of DeviceProxy.event_queue_size(...):

event_queue_size(self, event_id) -> int

Returns the number of stored events in the event reception buffer. After every call to DeviceProxy.get_events(), the event queue size is 0. During event subscription the client must have chosen the 'pull model' for this event. event_id is the event identifier returned by the DeviceProxy.subscribe_event() method.

Parameters

event_id (int) event identifier

Return an integer with the queue size

Throws *EventSystemFailed*

New in PyTango 7.0.0

get_config (*args, **kws)

This method is a simple way to do: self.get_device_proxy().get_attribute_config(self.name(), ...)

For convenience, here is the documentation of DeviceProxy.get_attribute_config(...):

get_attribute_config(self, name) -> AttributeInfoEx

Return the attribute configuration for a single attribute.

Parameters

name (str) attribute name

Return (*AttributeInfoEx*) Object containing the attribute information

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device

Deprecated: use get_attribute_config_ex instead

get_attribute_config(self, names) -> AttributeInfoList

Return the attribute configuration for the list of specified attributes. To get all the attributes pass a sequence containing the constant tango.class:constants.AllAttr

Parameters

names (sequence<str>) attribute names

Return (`AttributeInfoList`) Object containing the attributes information

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device, `TypeError`

Deprecated: use `get_attribute_config_ex` instead

get_device_proxy (*self*) → `DeviceProxy`

A method which returns the device associated to the attribute

Parameters None

Return (`DeviceProxy`)

get_events (**args, **kwargs*)

This method is a simple way to do: `self.get_device_proxy().get_events(...)`

For convenience, here is the documentation of `DeviceProxy.get_events(...)`:

`get_events(event_id, callback=None, extract_as=Numpy) -> None`

The method extracts all waiting events from the event reception buffer.

If callback is not None, it is executed for every event. During event subscription the client must have chosen the pull model for this event. The callback will receive a parameter of type `EventData`, `AttrConfEventData` or `DataReadyEventData` depending on the type of the event (`event_type` parameter of `subscribe_event`).

If callback is None, the method extracts all waiting events from the event reception buffer. The returned `event_list` is a vector of `EventData`, `AttrConfEventData` or `DataReadyEventData` pointers, just the same data the callback would have received.

Parameters

event_id (`int`) is the event identifier returned by the `DeviceProxy.subscribe_event()` method.

callback (`callable`) Any callable object or any object with a "push_event" method.

extract_as (`ExtractAs`)

Return None

Throws `EventSystemFailed`, `TypeError`, `ValueError`

See Also `subscribe_event`

New in PyTango 7.0.0

get_last_event_date (**args, **kwargs*)

This method is a simple way to do: `self.get_device_proxy().get_last_event_date(...)`

For convenience, here is the documentation of `DeviceProxy.get_last_event_date(...)`:

`get_last_event_date(self, event_id) -> TimeVal`

Returns the arrival time of the last event stored in the event reception buffer. After every call to `DeviceProxy.get_events()`, the event reception buffer is empty. In this case an exception will be returned. During event subscription the client must have chosen the 'pull model' for this event. `event_id` is the event identifier returned by the `DeviceProxy.subscribe_event()` method.

Parameters**event_id** (*int*) event identifier**Return** (*tango.TimeVal*) representing the arrival time**Throws** *EventSystemFailed**New in PyTango 7.0.0***get_poll_period** (*args, **kws)**This method is a simple way to do:** self.get_device_proxy().get_attribute_poll_period(self.name(), ...)

For convenience, here is the documentation of DeviceProxy.get_attribute_poll_period(...):

get_attribute_poll_period(self, attr_name) -> int

Return the attribute polling period.

Parameters**attr_name** (*str*) attribute name**Return** polling period in milliseconds**get_property** (self, propname, value) → DbData

Get a (list) property(ies) for an attribute.

This method accepts the following types as propname parameter: 1. string [in] - single property data to be fetched 2. sequence<string> [in] - several property data to be fetched 3. tango.DbDatum [in] - single property data to be fetched 4. tango.DbData [in,out] - several property data to be fetched. 5. sequence<DbDatum> - several property data to be fetched

Note: for cases 3, 4 and 5 the 'value' parameter if given, is IGNORED.

If value is given it must be a tango.DbData that will be filled with the property values

Parameters**propname** (*str*) property(ies) name(s)**value** (*tango.DbData*) (optional, default is None meaning that the method will create internally a tango.DbData and return it filled with the property values)**Return** (*DbData*) containing the property(ies) value(s). If a tango.DbData is given as parameter, it returns the same object otherwise a new tango.DbData is returned**Throws** *NonDbDevice*, *ConnectionFailed* (with database), *CommunicationFailed* (with database), *DevFailed* from database device**get_transparency_reconnection** (*args, **kws)**This method is a simple way to do:** self.get_device_proxy().get_transparency_reconnection(...)

For convenience, here is the documentation of DeviceProxy.get_transparency_reconnection(...):

get_transparency_reconnection(self) -> bool

Returns the device transparency reconnection flag.

Parameters None

Return (`bool`) True if transparency reconnection is set or False otherwise

history (*args, **kwargs)

This method is a simple way to do: `self.get_device_proxy().attribute_history(self.name(), ...)`

For convenience, here is the documentation of `DeviceProxy.attribute_history(...)`:

`attribute_history(self, attr_name, depth, extract_as=ExtractAs.Numpy) -> sequence<DeviceAttributeHistory>`

Retrieve attribute history from the attribute polling buffer. See chapter on Advanced Feature for all details regarding polling

Parameters

attr_name (`str`) Attribute name.

depth (`int`) The wanted history depth.

extract_as (`ExtractAs`)

Return This method returns a vector of `DeviceAttributeHistory` types.

Throws `NonSupportedFeature`, `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device

is_event_queue_empty (*args, **kwargs)

This method is a simple way to do: `self.get_device_proxy().is_event_queue_empty(...)`

For convenience, here is the documentation of `DeviceProxy.is_event_queue_empty(...)`:

`is_event_queue_empty(self, event_id) -> bool`

Returns true when the event reception buffer is empty. During event subscription the client must have chosen the 'pull model' for this event. `event_id` is the event identifier returned by the `DeviceProxy.subscribe_event()` method.

Parameters

event_id (`int`) event identifier

Return (`bool`) True if queue is empty or False otherwise

Throws `EventSystemFailed`

New in PyTango 7.0.0

is_polled (*args, **kwargs)

This method is a simple way to do: `self.get_device_proxy().is_attribute_polled(self.name(), ...)`

For convenience, here is the documentation of `DeviceProxy.is_attribute_polled(...)`:

`is_attribute_polled(self, attr_name) -> bool`

True if the attribute is polled.

Parameters

attr_name (`str`) attribute name

Return boolean value

name (*self*) → *str*

Returns the attribute name

Parameters None

Return (*str*) with the attribute name

ping (**args*, ***kwargs*)

This method is a simple way to do: `self.get_device_proxy().ping(...)`

For convenience, here is the documentation of `DeviceProxy.ping(...)`:

`ping(self) -> int`

A method which sends a ping to the device

Parameters None

Return (*int*) time elapsed in microseconds

Throws `exception` if device is not alive

poll (**args*, ***kwargs*)

This method is a simple way to do: `self.get_device_proxy().poll_attribute(self.name(), ...)`

For convenience, here is the documentation of `DeviceProxy.poll_attribute(...)`:

`poll_attribute(self, attr_name, period) -> None`

Add an attribute to the list of polled attributes.

Parameters

attr_name (*str*) attribute name

period (*int*) polling period in milliseconds

Return None

put_property (*self*, *value*) → None

Insert or update a list of properties for this attribute. This method accepts the following types as value parameter: 1. `tango.DbDatum` - single property data to be inserted 2. `tango.DbData` - several property data to be inserted 3. `sequence<DbDatum>` - several property data to be inserted 4. `dict<str, DbDatum>` - keys are property names and value has data to be inserted 5. `dict<str, seq<str>>` - keys are property names and value has data to be inserted 6. `dict<str, obj>` - keys are property names and `str(obj)` is property value

Parameters

value can be one of the following: 1. `tango.DbDatum` - single property data to be inserted 2. `tango.DbData` - several property data to be inserted 3. `sequence<DbDatum>` - several property data to be inserted 4. `dict<str, DbDatum>` - keys are property names and value has data to be inserted 5. `dict<str, seq<str>>` - keys are property names and value has data to be inserted 6. `dict<str, obj>` - keys are property names and `str(obj)` is property value

Return None

Throws `ConnectionFailed`, `CommunicationFailed` `DevFailed` from device (`DB_SQLError`), `TypeError`

`read(*args, **kwargs)`

This method is a simple way to do: `self.get_device_proxy().read_attribute(self.name(), ...)`

For convenience, here is the documentation of `DeviceProxy.read_attribute(...)`:

```
read_attribute(self, attr_name, extract_as=ExtractAs.Numpy,
green_mode=None, wait=True, timeout=None) -> DeviceAttribute
```

Read a single attribute.

Parameters

attr_name (`str`) The name of the attribute to read.

extract_as (`ExtractAs`) Defaults to `numpy`.

green_mode (`GreenMode`) Defaults to the current `DeviceProxy` `GreenMode`. (see `get_green_mode()` and `set_green_mode()`).

wait (`bool`) whether or not to wait for result. If `green_mode` is `Synchronous`, this parameter is ignored as it always waits for the result. Ignored when `green_mode` is `Synchronous` (always waits).

timeout (`float`) The number of seconds to wait for the result. If `None`, then there is no limit on the wait time. Ignored when `green_mode` is `Synchronous` or `wait` is `False`.

Return (`DeviceAttribute`)

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device `TimeoutError` (`green_mode == Futures`) If the future didn't finish executing before the given timeout. `Timeout` (`green_mode == Gevent`) If the async result didn't finish executing before the given timeout.

Changed in version 7.1.4: For `DevEncoded` attributes, before it was returning a `DeviceAttribute.value` as a tuple (**format<str>**, **data<str>**) no matter what was the `extract_as` value was. Since 7.1.4, it returns a (**format<str>**, **data<buffer>**) unless `extract_as` is `String`, in which case it returns (**format<str>**, **data<str>**).

Changed in version 8.0.0: For `DevEncoded` attributes, now returns a `DeviceAttribute.value` as a tuple (**format<str>**, **data<bytes>**) unless `extract_as` is `String`, in which case it returns (**format<str>**, **data<str>**). Carefull, if using python `>= 3` `data<str>` is decoded using default python `utf-8` encoding. This means that PyTango assumes tango DS was written encapsulating string into `utf-8` which is the default python encoding.

New in version 8.1.0: `green_mode` parameter. `wait` parameter. `timeout` parameter.

`read_async(*args, **kwargs)`

This method is a simple way to do: `self.get_device_proxy().read_attribute_async(self.name(), ...)`

For convenience, here is the documentation of `DeviceProxy.read_attribute_async(...)`:

```
read_attribute_async( self, attr_name) -> int
read_attribute_async( self, attr_name, callback) -> None
```

Shortcut to `self.read_attributes_async([attr_name], cb)`

New in PyTango 7.0.0

read_reply (*args, **kwargs)

This method is a simple way to do: self.get_device_proxy().read_attribute_reply(...)

For convenience, here is the documentation of DeviceProxy.read_attribute_reply(...):

```
read_attribute_reply( self, id, extract_as) -> int read_attribute_reply( self, id,
timeout, extract_as) -> None
```

Shortcut to self.read_attributes_reply()[0]

New in PyTango 7.0.0

set_config (*args, **kwargs)

This method is a simple way to do: self.get_device_proxy().set_attribute_config(...)

For convenience, here is the documentation of DeviceProxy.set_attribute_config(...):

```
set_attribute_config( self, attr_info) -> None
```

Change the attribute configuration for the specified attribute

Parameters

attr_info (*AttributeInfo*) attribute information

Return None

Throws *ConnectionFailed*, *CommunicationFailed*,
DevFailed from device, *TypeError*

```
set_attribute_config( self, attr_info_ex) -> None
```

Change the extended attribute configuration for the specified attribute

Parameters

attr_info_ex (*AttributeInfoEx*) extended attribute information

Return None

Throws *ConnectionFailed*, *CommunicationFailed*,
DevFailed from device, *TypeError*

```
set_attribute_config( self, attr_info) -> None
```

Change the attributes configuration for the specified attributes

Parameters

attr_info (sequence<*AttributeInfo*>) attributes information

Return None

Throws *ConnectionFailed*, *CommunicationFailed*,
DevFailed from device, *TypeError*

```
set_attribute_config( self, attr_info_ex) -> None
```

Change the extended attributes configuration for the specified attributes

Parameters

attr_info_ex (sequence<*AttributeInfoListEx*>) extended attributes information

Return None

Throws *ConnectionFailed*, *CommunicationFailed*,
DevFailed from device, *TypeError*

set_transparency_reconnection (*args, **kwargs)

This method is a simple way to do: self.get_device_proxy().set_transparency_reconnection(...)

For convenience, here is the documentation of DeviceProxy.set_transparency_reconnection(...):

set_transparency_reconnection(self, yesno) -> None

Set the device transparency reconnection flag

Parameters " - val : (bool) True to set transparency reconnection " or False otherwise

Return None

state (*args, **kwargs)

This method is a simple way to do: self.get_device_proxy().state(...)

For convenience, here is the documentation of DeviceProxy.state(...): **state** (self) -> *DevState*

A method which returns the state of the device.

Parameters None

Return (*DevState*) constant

Example

```
dev_st = dev.state()
if dev_st == DevState.ON : ...
```

status (*args, **kwargs)

This method is a simple way to do: self.get_device_proxy().status(...)

For convenience, here is the documentation of DeviceProxy.status(...): **status** (self) -> *str*

A method which returns the status of the device as a string.

Parameters None

Return (*str*) describing the device status

stop_poll (*args, **kwargs)

This method is a simple way to do: self.get_device_proxy().stop_poll_attribute(self.name(), ...)

For convenience, here is the documentation of DeviceProxy.stop_poll_attribute(...):

stop_poll_attribute(self, attr_name) -> None

Remove an attribute from the list of polled attributes.

Parameters

attr_name (*str*) attribute name

Return None

subscribe_event (*args, **kwargs)

This method is a simple way to do: self.get_device_proxy().subscribe_event(self.name(), ...)

For convenience, here is the documentation of DeviceProxy.subscribe_event(...):

subscribe_event(event_type, cb, stateless=False, green_mode=None) -> int

The client call to subscribe for event reception in the push model. The client implements a callback method which is triggered when the event is received. This method is currently used device interface change events only.

Parameters

event_type (*EventType*) Is the event reason and must be on the enumerated values: * EventType.INTERFACE_CHANGE_EVENT

callback (*callable*) Is any callable object or an object with a callable "push_event" method.

stateless (*bool*) When the this flag is set to false, an exception will be thrown when the event subscription encounters a problem. With the stateless flag set to true, the event subscription will always succeed, even if the corresponding device server is not running. The keep alive thread will try every 10 seconds to subscribe for the specified event. At every subscription retry, a callback is executed which contains the corresponding exception

green_mode the corresponding green mode (default is GreenMode.Synchronous)

Return An event id which has to be specified when unsubscribing from this event.

Throws *EventSystemFailed*, *TypeError*

subscribe_event(self, attr_name, event, callback, filters=[], stateless=False, extract_as=Numpy, green_mode=None) -> int

The client call to subscribe for event reception in the push model. The client implements a callback method which is triggered when the event is received. Filtering is done based on the reason specified and the event type. For example when reading the state and the reason specified is "change" the event will be fired only when the state changes. Events consist of an attribute name and the event reason. A standard set of reasons are implemented by the system, additional device specific reasons can be implemented by device servers programmers.

Parameters

attr_name (*str*) The device attribute name which will be sent as an event e.g. "current".

event_type (*EventType*) Is the event reason and must be on the enumerated values:
* EventType.CHANGE_EVENT
* EventType.PERIODIC_EVENT *

```

EventType.ARCHIVE_EVENT      *      Event-
Type.ATTR_CONF_EVENT        *      Event-
Type.DATA_READY_EVENT       *      Event-
Type.USER_EVENT

```

callback (*callable*) Is any callable object or an object with a callable “push_event” method.

filters (*sequence<str>*) A variable list of name,value pairs which define additional filters for events.

stateless (*bool*) When the this flag is set to false, an exception will be thrown when the event subscription encounters a problem. With the stateless flag set to true, the event subscription will always succeed, even if the corresponding device server is not running. The keep alive thread will try every 10 seconds to subscribe for the specified event. At every subscription retry, a callback is executed which contains the corresponding exception

extract_as (*ExtractAs*)

green_mode the corresponding green mode (default is *GreenMode.Synchronous*)

Return An event id which has to be specified when unsubscribing from this event.

Throws *EventSystemFailed*, *TypeError*

```

subscribe_event(self, attr_name, event, queuesize, filters=[], stateless=False,
green_mode=None) -> int

```

The client call to subscribe for event reception in the pull model. Instead of a `callback` method the client has to specify the size of the event reception buffer.

The event reception buffer is implemented as a round robin buffer. This way the client can set-up different ways to receive events:

- Event reception buffer size = 1 : The client is interested only in the value of the last event received. All other events that have been received since the last reading are discarded.
- Event reception buffer size > 1 : The client has chosen to keep an event history of a given size. When more events arrive since the last reading, older events will be discarded.
- Event reception buffer size = `ALL_EVENTS` : The client buffers all received events. The buffer size is unlimited and only restricted by the available memory for the client.

All other parameters are similar to the descriptions given in the other `subscribe_event()` version.

```

unsubscribe_event (*args, **kws)

```

This method is a simple way to do: `self.get_device_proxy().unsubscribe_event(...)`

For convenience, here is the documentation of `DeviceProxy.unsubscribe_event(...)`:

```

unsubscribe_event(self, event_id) -> None

```

Unsubscribes a client from receiving the event specified by `event_id`.

Parameters

event_id (*int*) is the event identifier returned by the `DeviceProxy::subscribe_event()`. Unlike in TangoC++ we check that the `event_id` has been subscribed in this `DeviceProxy`.

Return `None`

Throws `EventSystemFailed`, `KeyError`

write (**args, **kwargs*)

This method is a simple way to do: `self.get_device_proxy().write_attribute(self.name(), ...)`

For convenience, here is the documentation of `DeviceProxy.write_attribute(...)`:

`write_attribute(self, attr_name, value, green_mode=None, wait=True, timeout=None) -> None`
`write_attribute(self, attr_info, value, green_mode=None, wait=True, timeout=None) -> None`

Write a single attribute.

Parameters

attr_name (*str*) The name of the attribute to write.

attr_info (*AttributeInfo*)

value The value. For non SCALAR attributes it may be any sequence of sequences.

green_mode (*GreenMode*) Defaults to the current `DeviceProxy GreenMode`. (see `get_green_mode()` and `set_green_mode()`).

wait (*bool*) whether or not to wait for result. If `green_mode` is *Synchronous*, this parameter is ignored as it always waits for the result. Ignored when `green_mode` is *Synchronous* (always waits).

timeout (*float*) The number of seconds to wait for the result. If `None`, then there is no limit on the wait time. Ignored when `green_mode` is *Synchronous* or `wait` is `False`.

Throws `ConnectionFailed`, `CommunicationFailed`, `DeviceUnlocked`, `DevFailed` from device `TimeoutError` (`green_mode == Futures`) If the future didn't finish executing before the given timeout. `Timeout` (`green_mode == Gevent`) If the async result didn't finish executing before the given timeout.

New in version 8.1.0: `green_mode` parameter. `wait` parameter. `timeout` parameter.

write_async (**args, **kwargs*)

This method is a simple way to do: `self.get_device_proxy().write_attribute_async(...)`

For convenience, here is the documentation of `DeviceProxy.write_attribute_async(...)`:

`write_attributes_async(self, values) -> int`
`write_attributes_async(self, values, callback) -> None`

Shortcut to `self.write_attributes_async([attr_name, value], cb)`

New in PyTango 7.0.0

write_read(*args, **kwargs)

This method is a simple way to do: self.get_device_proxy().write_read_attribute(self.name(), ...)

For convenience, here is the documentation of DeviceProxy.write_read_attribute(...):

write_read_attribute(self, attr_name, value, extract_as=ExtractAs.Numpy, green_mode=None, wait=True, timeout=None) -> DeviceAttribute

Write then read a single attribute in a single network call. By default (serialisation by device), the execution of this call in the server can't be interrupted by other clients.

Parameters see write_attribute(attr_name, value)

Return A tango.DeviceAttribute object.

Throws *ConnectionFailed*, *CommunicationFailed*, *DeviceUnlocked*, *DevFailed* from device, *WrongData* TimeoutError (green_mode == Futures) If the future didn't finish executing before the given timeout. Timeout (green_mode == Gevent) If the async result didn't finish executing before the given timeout.

New in PyTango 7.0.0

New in version 8.1.0: *green_mode* parameter. *wait* parameter. *timeout* parameter.

write_reply(*args, **kwargs)

This method is a simple way to do: self.get_device_proxy().write_attribute_reply(...)

For convenience, here is the documentation of DeviceProxy.write_attribute_reply(...):

write_attribute_reply(self, id) -> None

Check if the answer of an asynchronous write_attribute is arrived (polling model). If the reply is arrived and if it is a valid reply, the call returned. If the reply is an exception, it is re-thrown by this call. An exception is also thrown in case of the reply is not yet arrived.

Parameters

id (*int*) the asynchronous call identifier.

Return None

Throws *AsyncCall*, *AsynReplyNotArrived*, *CommunicationFailed*, *DevFailed* from device.

New in PyTango 7.0.0

write_attribute_reply(self, id, timeout) -> None

Check if the answer of an asynchronous write_attribute is arrived (polling model). id is the asynchronous call identifier. If the reply is arrived and if it is a valid reply, the call returned. If the reply is an exception, it is re-thrown by this call. If the reply is not yet arrived, the call will wait (blocking the process) for the time specified in timeout. If after timeout milliseconds, the reply is still not there, an exception is thrown. If timeout is set to 0, the call waits until the reply arrived.

Parameters

id (*int*) the asynchronous call identifier.

timeout (*int*) the timeout

Return None

Throws *AsyncCall*, *AsyncReplyNotArrived*,
CommunicationFailed, *DevFailed* from device.

New in PyTango 7.0.0

5.2.3 Group

Group class

class `tango.Group` (*name*)

Bases: `object`

A Tango Group represents a hierarchy of tango devices. The hierarchy may have more than one level. The main goal is to group devices with same attribute(s)/command(s) to be able to do parallel requests.

add (*self*, *subgroup*, *timeout_ms=-1*) → None

Attaches a (sub)_RealGroup.

To remove the subgroup use the `remove()` method.

Parameters

subgroup (*str*)

timeout_ms (*int*) If `timeout_ms` parameter is different from -1, the client side timeout associated to each device composing the `_RealGroup` added is set to `timeout_ms` milliseconds. If `timeout_ms` is -1, timeouts are not changed.

Return None

Throws `TypeError`, `ArgumentError`

command_inout (*self*, *cmd_name*, *forward=True*) → `sequence<GroupCmdReply>`

command_inout (*self*, *cmd_name*, *param*, *forward=True*) → `sequence<GroupCmdReply>`

command_inout (*self*, *cmd_name*, *param_list*, *forward=True*) → `sequence<GroupCmdReply>`

Just a shortcut to do: `self.command_inout_reply(self.command_inout_async(...))`

Parameters

cmd_name (*str*) Command name

param (*any*) parameter value

param_list (`tango.DeviceDataList`) sequence of parameters. When given, it's length must match the group size.

forward (*bool*) If it is set to true (the default) request is forwarded to subgroups. Otherwise, it is only applied to the local set of devices.

Return (`sequence<GroupCmdReply>`)

```
command_inout_async (self, cmd_name, forget=False, forward=True, reserved=-1) → int
command_inout_async (self, cmd_name, param, forget=False, forward=True, reserved=-1) → int
command_inout_async (self, cmd_name, param_list, forget=False, forward=True, reserved=-1) → int
```

Executes a Tango command on each device in the group asynchronously. The method sends the request to all devices and returns immediately. Pass the returned request id to `Group.command_inout_reply()` to obtain the results.

Parameters

cmd_name (*str*) Command name

param (*any*) parameter value

param_list (*tango.DeviceDataList*) sequence of parameters. When given, it's length must match the group size.

forget (*bool*) Fire and forget flag. If set to true, it means that no reply is expected (i.e. the caller does not care about it and will not even try to get it)

forward (*bool*) If it is set to true (the default) request is forwarded to subgroups. Otherwise, it is only applied to the local set of devices.

reserved (*int*) is reserved for internal purpose and should not be used. This parameter may disappear in a near future.

Return (*int*) request id. Pass the returned request id to `Group.command_inout_reply()` to obtain the results.

Throws

```
command_inout_reply (self, req_id, timeout_ms=0) → sequence<GroupCmdReply>
```

Returns the results of an asynchronous command.

Parameters

req_id (*int*) Is a request identifier previously returned by one of the `command_inout_async` methods

timeout_ms (*int*) For each device in the hierarchy, if the command result is not yet available, `command_inout_reply` wait `timeout_ms` milliseconds before throwing an exception. This exception will be part of the global reply. If `timeout_ms` is set to 0, `command_inout_reply` waits "indefinitely".

Return (*sequence<GroupCmdReply>*)

Throws

```
contains (self, pattern, forward=True) → bool
```

Parameters

pattern (*str*) The pattern can be a fully qualified or simple group name, a device name or a device name pattern.

forward (*bool*) If fwd is set to true (the default), the remove request is also forwarded to subgroups. Otherwise, it is only applied to the local set of elements.

Return (*bool*) Returns true if the hierarchy contains groups and/or devices which name matches the specified pattern. Returns false otherwise.

Throws

disable (**args, **kwargs*)

Disables a group or a device element in a group.

enable (**args, **kwargs*)

Enables a group or a device element in a group.

get_device_list (*self, forward=True*) → *sequence<str>*

Considering the following hierarchy:

```
g2.add("my/device/04")
g2.add("my/device/05")

g4.add("my/device/08")
g4.add("my/device/09")

g3.add("my/device/06")
g3.add(g4)
g3.add("my/device/07")

g1.add("my/device/01")
g1.add(g2)
g1.add("my/device/03")
g1.add(g3)
g1.add("my/device/02")
```

The returned vector content depends on the value of the forward option. If set to true, the results will be organized as follows:

```
dl = g1.get_device_list(True)

dl[0] contains "my/device/01" which belongs to g1
dl[1] contains "my/device/04" which belongs to g1.g2
dl[2] contains "my/device/05" which belongs to g1.g2
dl[3] contains "my/device/03" which belongs to g1
dl[4] contains "my/device/06" which belongs to g1.g3
dl[5] contains "my/device/08" which belongs to g1.g3.g4
dl[6] contains "my/device/09" which belongs to g1.g3.g4
dl[7] contains "my/device/07" which belongs to g1.g3
dl[8] contains "my/device/02" which belongs to g1
```

If the forward option is set to false, the results are:

```
dl = g1.get_device_list(False);

dl[0] contains "my/device/01" which belongs to g1
dl[1] contains "my/device/03" which belongs to g1
dl[2] contains "my/device/02" which belongs to g1
```

Parameters

forward (*bool*) If it is set to true (the default), the request is forwarded to sub-groups. Otherwise, it is only applied to the local set of devices.

Return (*sequence<str>*) The list of devices currently in the hierarchy.

Throws**get_fully_qualified_name** (*args, **kwargs)

Get the complete (dpt-separated) name of the group. This takes into consideration the name of the group and its parents.

get_name (*args, **kwargs)

Get the name of the group. Eg: Group('name').get_name() == 'name'

get_size (self, forward=True) → int**Parameters**

forward (bool) If it is set to true (the default), the request is forwarded to sub-groups.

Return (int) The number of the devices in the hierarchy

Throws**is_enabled** (*args, **kwargs)

Check if a group is enabled. *New in PyTango 7.0.0*

name_equals (*args, **kwargs)

New in PyTango 7.0.0

name_matches (*args, **kwargs)

New in PyTango 7.0.0

ping (self, forward=True) → bool

Ping all devices in a group.

Parameters

forward (bool) If fwd is set to true (the default), the request is also forwarded to subgroups. Otherwise, it is only applied to the local set of devices.

Return (bool) This method returns true if all devices in the group are alive, false otherwise.

Throws**read_attribute** (self, attr_name, forward=True) → sequence<GroupAttrReply>

Just a shortcut to do: self.read_attribute_reply(self.read_attribute_async(...))

read_attribute_async (self, attr_name, forward=True, reserved=-1) → int

Reads an attribute on each device in the group asynchronously. The method sends the request to all devices and returns immediately.

Parameters

attr_name (str) Name of the attribute to read.

forward (bool) If it is set to true (the default) request is forwarded to subgroups. Otherwise, it is only applied to the local set of devices.

reserved (int) is reserved for internal purpose and should not be used. This parameter may disappear in a near future.

Return (int) request id. Pass the returned request id to Group.read_attribute_reply() to obtain the results.

Throws

read_attribute_reply (*self*, *req_id*, *timeout_ms=0*) → sequence<GroupAttrReply>

Returns the results of an asynchronous attribute reading.

Parameters

req_id (*int*) a request identifier previously returned by `read_attribute_async`.

timeout_ms (*int*) For each device in the hierarchy, if the attribute value is not yet available, `read_attribute_reply` wait `timeout_ms` milliseconds before throwing an exception. This exception will be part of the global reply. If `timeout_ms` is set to 0, `read_attribute_reply` waits “indefinitely”.

Return (sequence<GroupAttrReply>)

Throws

read_attributes (*self*, *attr_names*, *forward=True*) → sequence<GroupAttrReply>

Just a shortcut to do: `self.read_attributes_reply(self.read_attributes_async(...))`

read_attributes_async (*self*, *attr_names*, *forward=True*, *reserved=-1*) → *int*

Reads the attributes on each device in the group asynchronously. The method sends the request to all devices and returns immediately.

Parameters

attr_names (sequence<str>) Name of the attributes to read.

forward (*bool*) If it is set to true (the default) request is forwarded to subgroups. Otherwise, it is only applied to the local set of devices.

reserved (*int*) is reserved for internal purpose and should not be used. This parameter may disappear in a near future.

Return (*int*) request id. Pass the returned request id to `Group.read_attributes_reply()` to obtain the results.

Throws

read_attributes_reply (*self*, *req_id*, *timeout_ms=0*) → sequence<GroupAttrReply>

Returns the results of an asynchronous attribute reading.

Parameters

req_id (*int*) a request identifier previously returned by `read_attribute_async`.

timeout_ms (*int*) For each device in the hierarchy, if the attribute value is not yet available, `read_attribute_reply` wait `timeout_ms` milliseconds before throwing an exception. This exception will be part of the global reply. If `timeout_ms` is set to 0, `read_attributes_reply` waits “indefinitely”.

Return (sequence<GroupAttrReply>)

Throws

remove_all (*self*) → None

Removes all elements in the `_RealGroup`. After such a call, the `_RealGroup` is empty.

set_timeout_millis (*self*, *timeout_ms*) → *bool*

Set client side timeout for all devices composing the group in milliseconds. Any method which takes longer than this time to execute will throw an exception.

Parameters

timeout_ms (*int*)

Return None

Throws (errors are ignored)

New in PyTango 7.0.0

write_attribute (*self, attr_name, value, forward=True, multi=False*) → *sequence<GroupReply>*

Just a shortcut to do: `self.write_attribute_reply(self.write_attribute_async(...))`

write_attribute_async (*self, attr_name, value, forward=True, multi=False*) → *int*

Writes an attribute on each device in the group asynchronously. The method sends the request to all devices and returns immediately.

Parameters

attr_name (*str*) Name of the attribute to write.

value (*any*) Value to write. See `DeviceProxy.write_attribute`

forward (*bool*) If it is set to true (the default) request is forwarded to subgroups. Otherwise, it is only applied to the local set of devices.

multi (*bool*) If it is set to false (the default), the same value is applied to all devices in the group. Otherwise the value is interpreted as a sequence of values, and each value is applied to the corresponding device in the group. In this case `len(value)` must be equal to `group.get_size()`!

Return (*int*) request id. Pass the returned request id to `Group.write_attribute_reply()` to obtain the acknowledgements.

Throws

write_attribute_reply (*self, req_id, timeout_ms=0*) → *sequence<GroupReply>*

Returns the acknowledgements of an asynchronous attribute writing.

Parameters

req_id (*int*) a request identifier previously returned by `write_attribute_async`.

timeout_ms (*int*) For each device in the hierarchy, if the acknowledgment is not yet available, `write_attribute_reply` wait `timeout_ms` milliseconds before throwing an exception. This exception will be part of the global reply. If `timeout_ms` is set to 0, `write_attribute_reply` waits "indefinitely".

Return (*sequence<GroupReply>*)

Throws

GroupReply classes

Group member functions do not return the same as their DeviceProxy counterparts, but objects that contain them. This is:

- *write attribute* family returns `tango.GroupReplyList`
- *read attribute* family returns `tango.GroupAttrReplyList`
- *command inout* family returns `tango.GroupCmdReplyList`

The Group*ReplyList objects are just list-like objects containing `GroupReply`, `GroupAttrReply` and `GroupCmdReply` elements that will be described now.

Note also that `GroupReply` is the base of `GroupCmdReply` and `GroupAttrReply`.

class `tango.GroupReply`

This is the base class for the result of an operation on a `PyTangoGroup`, being it a write attribute, read attribute, or command inout operation.

It has some trivial common operations:

- `has_failed(self)` -> bool
- `group_element_enabled(self)` ->bool
- `dev_name(self)` -> str
- `obj_name(self)` -> str
- `get_err_stack(self)` -> `DevErrorList`

class `tango.GroupAttrReply`

`get_data` (*self*, *extract_as*=`ExtractAs.Numpy`) → `DeviceAttribute`

Get the `DeviceAttribute`.

Parameters

extract_as (`ExtractAs`)

Return (`DeviceAttribute`) Whatever is stored there, or None.

class `tango.GroupCmdReply`

`get_data` (*self*) → any

Get the actual value stored in the `GroupCmdRply`, the command output value. It's the same as `self.get_data_raw().extract()`

Parameters None

Return (any) Whatever is stored there, or None.

`get_data_raw` (*self*) → any

Get the `DeviceData` containing the output parameter of the command.

Parameters None

Return (`DeviceData`) Whatever is stored there, or None.

5.2.4 Green API

Summary:

- `tango.get_green_mode()`
- `tango.set_green_mode()`
- `tango.futures.DeviceProxy()`
- `tango.gevent.DeviceProxy()`

`tango.get_green_mode()`

Returns the current global default PyTango green mode.

Returns the current global default PyTango green mode

Return type *GreenMode*

`tango.set_green_mode(green_mode=None)`

Sets the global default PyTango green mode.

Advice: Use only in your final application. Don't use this in a python library in order not to interfere with the behavior of other libraries and/or application where your library is being.

Parameters `green_mode` (*GreenMode*) – the new global default PyTango green mode

`tango.futures.DeviceProxy(self, dev_name, wait=True, timeout=True) → DeviceProxy`

`DeviceProxy(self, dev_name, need_check_acc, wait=True, timeout=True) -> DeviceProxy`

Creates a *futures* enabled *DeviceProxy*.

The *DeviceProxy* constructor internally makes some network calls which makes it *slow*. By using the *futures green mode* you are allowing other python code to be executed in a cooperative way.

Note: The `timeout` parameter has no relation with the tango device client side timeout (gettable by `get_timeout_millis()` and settable through `set_timeout_millis()`)

Parameters

- **dev_name** (*str*) – the device name or alias
- **need_check_acc** (*bool*) – in first version of the function it defaults to True. Determines if at creation time of *DeviceProxy* it should check for channel access (rarely used)
- **wait** (*bool*) – whether or not to wait for result of creating a *DeviceProxy*.
- **timeout** (*float*) – The number of seconds to wait for the result. If None, then there is no limit on the wait time. Ignored when `wait` is False.

Returns

if wait is True: *DeviceProxy*

else: `concurrent.futures.Future`

Throws

- a *DevFailed* if `wait` is True and there is an error creating the device.
- a *concurrent.futures.TimeoutError* if `wait` is False, `timeout` is not None and the time to create the device has expired.

New in PyTango 8.1.0

`tango.gevent.DeviceProxy(self, dev_name, wait=True, timeout=True) → DeviceProxy`

`DeviceProxy(self, dev_name, need_check_acc, wait=True, timeout=True) -> DeviceProxy`

Creates a *gevent* enabled *DeviceProxy*.

The DeviceProxy constructor internally makes some network calls which makes it *slow*. By using the gevent *green mode* you are allowing other python code to be executed in a cooperative way.

Note: The timeout parameter has no relation with the tango device client side timeout (gettable by `get_timeout_millis()` and settable through `set_timeout_millis()`)

Parameters

- **dev_name** (*str*) – the device name or alias
- **need_check_acc** (*bool*) – in first version of the function it defaults to True. Determines if at creation time of DeviceProxy it should check for channel access (rarely used)
- **wait** (*bool*) – whether or not to wait for result of creating a DeviceProxy.
- **timeout** (*float*) – The number of seconds to wait for the result. If None, then there is no limit on the wait time. Ignored when wait is False.

Returns

if wait is True: `DeviceProxy`
else: `gevent.event.AsyncResult`

Throws

- a `DevFailed` if wait is True and there is an error creating the device.
- a `gevent.timeout.Timeout` if wait is False, timeout is not None and the time to create the device has expired.

New in PyTango 8.1.0

5.2.5 API util

`class` `tango.ApiUtil`

This class allows you to access the tango synchronization model API. It is designed as a singleton. To get a reference to the singleton object you must do:

```
import tango
apiutil = tango.ApiUtil.instance()
```

New in PyTango 7.1.3

get_async_cb_sub_model (*self*) → `cb_sub_model`

Get the asynchronous callback sub-model.

Parameters None

Return (`cb_sub_model`) the active asynchronous callback sub-model.

New in PyTango 7.1.3

get_async_replies (*self*) → `None`

Fire callback methods for all (any device) asynchronous requests (command and attribute) with already arrived replied. Returns immediately if there is no replies already arrived or if there is no asynchronous requests.

Parameters None

Return None

Throws None, all errors are reported using the `err` and `errors` fields of the parameter passed to the `callback` method.

New in PyTango 7.1.3

get_async_replies (*self*) -> None

Fire callback methods for all (any device) asynchronous requests (command and attributes) with already arrived replied. Wait and block the caller for timeout milliseconds if they are some device asynchronous requests which are not yet arrived. Returns immediately if there is no asynchronous request. If timeout is set to 0, the call waits until all the asynchronous requests sent has received a reply.

Parameters

timeout (`int`) timeout (milliseconds)

Return None

Throws *AsynReplyNotArrived*. All other errors are reported using the `err` and `errors` fields of the object passed to the `callback` methods.

New in PyTango 7.1.3

pending_async_call (*self, req*) → `int`

Return number of asynchronous pending requests (any device). The input parameter is an enumeration with three values which are:

- POLLING: Return only polling model asynchronous request number
- CALL_BACK: Return only callback model asynchronous request number
- ALL_ASYNC: Return all asynchronous request number

Parameters

req (*asyn_req_type*) asynchronous request type

Return (`int`) the number of pending requests for the given type

New in PyTango 7.1.3

set_async_cb_sub_model (*self, model*) → None

Set the asynchronous callback sub-model between the pull and push sub-model. The `cb_sub_model` data type is an enumeration with two values which are:

- PUSH_CALLBACK: The push sub-model
- PULL_CALLBACK: The pull sub-model

Parameters

model (*cb_sub_model*) the callback sub-model

Return None

New in PyTango 7.1.3

5.2.6 Information classes

See also *Event configuration information*

Attribute

class tango.AttributeAlarmInfo

A structure containing available alarm information for an attribute with the following members:

- min_alarm : (str) low alarm level
- max_alarm : (str) high alarm level
- min_warning : (str) low warning level
- max_warning : (str) high warning level
- delta_t : (str) time delta
- delta_val : (str) value delta
- extensions : (StdStringVector) extensions (currently not used)

class tango.AttributeDimension

A structure containing x and y attribute data dimensions with the following members:

- dim_x : (int) x dimension
- dim_y : (int) y dimension

class tango.AttributeInfo

A structure (inheriting from *DeviceAttributeConfig*) containing available information for an attribute with the following members:

- disp_level : (*DispLevel*) display level (OPERATOR, EXPERT)

Inherited members are:

- name : (str) attribute name
- writable : (*AttrWriteType*) write type (R, W, RW, R with W)
- data_format : (*AttrDataFormat*) data format (SCALAR, SPECTRUM, IMAGE)
- data_type : (int) attribute type (float, string,...)
- max_dim_x : (int) first dimension of attribute (spectrum or image attributes)
- max_dim_y : (int) second dimension of attribute(image attribute)
- description : (int) attribute description
- label : (str) attribute label (Voltage, time, ...)
- unit : (str) attribute unit (V, ms, ...)
- standard_unit : (str) standard unit
- display_unit : (str) display unit
- format : (str) how to display the attribute value (ex: for floats could be '%6.2f')
- min_value : (str) minimum allowed value
- max_value : (str) maximum allowed value
- min_alarm : (str) low alarm level
- max_alarm : (str) high alarm level
- writable_attr_name : (str) name of the writable attribute
- extensions : (StdStringVector) extensions (currently not used)

class tango.AttributeInfoEx

A structure (inheriting from *AttributeInfo*) containing available information for an attribute with the following members:

- alarms : object containing alarm information (see AttributeAlarmInfo).

- `events` : object containing event information (see `AttributeEventInfo`).
- `sys_extensions` : `StdStringVector`

Inherited members are:

- `name` : (`str`) attribute name
- `writable` : (`AttrWriteType`) write type (R, W, RW, R with W)
- `data_format` : (`AttrDataFormat`) data format (SCALAR, SPECTRUM, IMAGE)
- `data_type` : (`int`) attribute type (float, string,...)
- `max_dim_x` : (`int`) first dimension of attribute (spectrum or image attributes)
- `max_dim_y` : (`int`) second dimension of attribute(image attribute)
- `description` : (`int`) attribute description
- `label` : (`str`) attribute label (Voltage, time, ...)
- `unit` : (`str`) attribute unit (V, ms, ...)
- `standard_unit` : (`str`) standard unit
- `display_unit` : (`str`) display unit
- `format` : (`str`) how to display the attribute value (ex: for floats could be `'%6.2f'`)
- `min_value` : (`str`) minimum allowed value
- `max_value` : (`str`) maximum allowed value
- `min_alarm` : (`str`) low alarm level
- `max_alarm` : (`str`) high alarm level
- `writable_attr_name` : (`str`) name of the writable attribute
- `extensions` : (`StdStringVector`) extensions (currently not used)
- `disp_level` : (`DispLevel`) display level (OPERATOR, EXPERT)

see also [AttributeInfo](#)

class `tango.DeviceAttributeConfig`

A base structure containing available information for an attribute with the following members:

- `name` : (`str`) attribute name
- `writable` : (`AttrWriteType`) write type (R, W, RW, R with W)
- `data_format` : (`AttrDataFormat`) data format (SCALAR, SPECTRUM, IMAGE)
- `data_type` : (`int`) attribute type (float, string,...)
- `max_dim_x` : (`int`) first dimension of attribute (spectrum or image attributes)
- `max_dim_y` : (`int`) second dimension of attribute(image attribute)
- `description` : (`int`) attribute description
- `label` : (`str`) attribute label (Voltage, time, ...)
- `unit` : (`str`) attribute unit (V, ms, ...)
- `standard_unit` : (`str`) standard unit
- `display_unit` : (`str`) display unit
- `format` : (`str`) how to display the attribute value (ex: for floats could be `'%6.2f'`)
- `min_value` : (`str`) minimum allowed value
- `max_value` : (`str`) maximum allowed value
- `min_alarm` : (`str`) low alarm level
- `max_alarm` : (`str`) high alarm level
- `writable_attr_name` : (`str`) name of the writable attribute
- `extensions` : (`StdStringVector`) extensions (currently not used)

Command

class tango.DevCommandInfo

A device command info with the following members:

- `cmd_name` : (*str*) command name
- `cmd_tag` : command as binary value (for TACO)
- `in_type` : (*CmdArgType*) input type
- `out_type` : (*CmdArgType*) output type
- `in_type_desc` : (*str*) description of input type
- `out_type_desc` : (*str*) description of output type

New in PyTango 7.0.0

class tango.CommandInfo

A device command info (inheriting from *DevCommandInfo*) with the following members:

- `disp_level` : (*DispLevel*) command display level

Inherited members are (from *DevCommandInfo*):

- `cmd_name` : (*str*) command name
- `cmd_tag` : (*str*) command as binary value (for TACO)
- `in_type` : (*CmdArgType*) input type
- `out_type` : (*CmdArgType*) output type
- `in_type_desc` : (*str*) description of input type
- `out_type_desc` : (*str*) description of output type

Other

class tango.DeviceInfo

A structure containing available information for a device with the following members:

- `dev_class` : (*str*) device class
- `server_id` : (*str*) server ID
- `server_host` : (*str*) host name
- `server_version` : (*str*) server version
- `doc_url` : (*str*) document url

class tango.LockerInfo

A structure with information about the locker with the following members:

- `ll` : (*tango.LockerLanguage*) the locker language
- `li` : (*pid_t* / *UUID*) the locker id
- `locker_host` : (*str*) the host
- `locker_class` : (*str*) the class

`pid_t` should be an *int*, *UUID* should be a tuple of four numbers.

New in PyTango 7.0.0

class tango.PollDevice

A structure containing PollDevice information with the following members:

- `dev_name` : (*str*) device name
- `ind_list` : (*sequence<int>*) index list

New in PyTango 7.0.0

5.2.7 Storage classes

Attribute: DeviceAttribute

class tango.DeviceAttribute

This is the fundamental type for RECEIVING data from device attributes.

It contains several fields. The most important ones depend on the ExtractAs method used to get the value. Normally they are:

- `value` : Normal scalar value or numpy array of values.
- `w_value` : The write part of the attribute.

See other ExtractAs for different possibilities. There are some more fields, these really fixed:

- `name` : (`str`)
- `data_format` : (`AttrDataFormat`) Attribute format
- `quality` : (`AttrQuality`)
- `time` : (`TimeVal`)
- `dim_x` : (`int`) attribute dimension x
- `dim_y` : (`int`) attribute dimension y
- `w_dim_x` : (`int`) attribute written dimension x
- `w_dim_y` : (`int`) attribute written dimension y
- `r_rimension` : (`tuple`) Attribute read dimensions.
- `w_dimension` : (`tuple`) Attribute written dimensions.
- `nb_read` : (`int`) attribute read total length
- `nb_written` : (`int`) attribute written total length

And two methods:

- `get_date`
- `get_err_stack`

```
ExtractAs = <ExtensionMock name='_tango.ExtractAs' id='140349538852672'>
```

```
get_date (self) → TimeVal
```

Get the time at which the attribute was read by the server.

Note: It's the same as reading the "time" attribute.

Parameters None

Return (`TimeVal`) The attribute read timestamp.

```
get_err_stack (self) → sequence<DevError>
```

Returns the error stack reported by the server when the attribute was read.

Parameters None

Return (sequence<`DevError`>)

```
set_w_dim_x (self, val) → None
```

Sets the write value dim x.

Parameters

val (`int`) new write dim x

Return None

New in PyTango 8.0.0

```
set_w_dim_y (self, val) → None
```

Sets the write value dim y.

Parameters

`val (int) new write dim y`

Return None

New in PyTango 8.0.0

Command: DeviceData

Device data is the type used internally by Tango to deal with command parameters and return values. You don't usually need to deal with it, as `command_inout` will automatically convert the parameters from any other type and the result value to another type.

You can still use them, using `command_inout_raw` to get the result in a `DeviceData`.

You also may deal with it when reading command history.

class `tango.DeviceData`

This is the fundamental type for sending and receiving data from device commands. The values can be inserted and extracted using the `insert()` and `extract()` methods.

extract (*self*) → any

Get the actual value stored in the `DeviceData`.

Parameters None

Return Whatever is stored there, or None.

get_type (*self*) → `CmdArgType`

This method returns the Tango data type of the data inside the `DeviceData` object.

Parameters None

Return The content arg type.

insert (*self*, *data_type*, *value*) → None

Inserts a value in the `DeviceData`.

Parameters

data_type

value (any) The value to insert

Return Whatever is stored there, or None.

is_empty (*self*) → bool

It can be used to test whether the `DeviceData` object has been initialized or not.

Parameters None

Return True or False depending on whether the `DeviceData` object contains data or not.

5.2.8 Callback related classes

If you subscribe a callback in a DeviceProxy, it will be run with a parameter. This parameter depends will be of one of the following classes depending on the callback type.

class tango.AttrReadEvent

This class is used to pass data to the callback method in asynchronous callback model for read_attribute(s) execution.

It has the following members:

- device : (*DeviceProxy*) The DeviceProxy object on which the call was executed
- attr_names : (sequence<str>) The attribute name list
- argout : (*DeviceAttribute*) The attribute value
- err : (bool) A boolean flag set to true if the command failed. False otherwise
- errors : (sequence<DevError>) The error stack
- ext :

class tango.AttrWrittenEvent

This class is used to pass data to the callback method in asynchronous callback model for write_attribute(s) execution

It has the following members:

- device : (*DeviceProxy*) The DeviceProxy object on which the call was executed
- attr_names : (sequence<str>) The attribute name list
- err : (bool) A boolean flag set to true if the command failed. False otherwise
- errors : (*NamedDevFailedList*) The error stack
- ext :

class tango.CmdDoneEvent

This class is used to pass data to the callback method in asynchronous callback model for command execution.

It has the following members:

- device : (*DeviceProxy*) The DeviceProxy object on which the call was executed.
- cmd_name : (str) The command name
- argout_raw : (*DeviceData*) The command argout
- argout : The command argout
- err : (bool) A boolean flag set to true if the command failed. False otherwise
- errors : (sequence<DevError>) The error stack
- ext :

5.2.9 Event related classes

Event configuration information

class tango.AttributeEventInfo

A structure containing available event information for an attribute with the following members:

- ch_event : (*ChangeEventInfo*) change event information
- per_event : (*PeriodicEventInfo*) periodic event information
- arch_event : (*ArchiveEventInfo*) archiving event information

class tango.**ArchiveEventInfo**

A structure containing available archiving event information for an attribute with the following members:

- `archive_rel_change` : (`str`) relative change that will generate an event
- `archive_abs_change` : (`str`) absolute change that will generate an event
- `archive_period` : (`str`) archive period
- `extensions` : (sequence<`str`>) extensions (currently not used)

class tango.**ChangeEventInfo**

A structure containing available change event information for an attribute with the following members:

- `rel_change` : (`str`) relative change that will generate an event
- `abs_change` : (`str`) absolute change that will generate an event
- `extensions` : (`StdStringVector`) extensions (currently not used)

class tango.**PeriodicEventInfo**

A structure containing available periodic event information for an attribute with the following members:

- `period` : (`str`) event period
- `extensions` : (`StdStringVector`) extensions (currently not used)

Event arrived structures

class tango.**EventData**

This class is used to pass data to the callback method when an event is sent to the client. It contains the following public fields:

- `device` : (`DeviceProxy`) The DeviceProxy object on which the call was executed.
- `attr_name` : (`str`) The attribute name
- `event` : (`str`) The event name
- `attr_value` : (`DeviceAttribute`) The attribute data (DeviceAttribute)
- `err` : (`bool`) A boolean flag set to true if the request failed. False otherwise
- `errors` : (sequence<`DevError`>) The error stack
- `reception_date`: (`TimeVal`)

class tango.**AttrConfEventData**

This class is used to pass data to the callback method when a configuration event is sent to the client. It contains the following public fields:

- `device` : (`DeviceProxy`) The DeviceProxy object on which the call was executed
- `attr_name` : (`str`) The attribute name
- `event` : (`str`) The event name
- `attr_conf` : (`AttributeInfoEx`) The attribute data
- `err` : (`bool`) A boolean flag set to true if the request failed. False otherwise
- `errors` : (sequence<`DevError`>) The error stack
- `reception_date`: (`TimeVal`)

class tango.**DataReadyEventData**

This class is used to pass data to the callback method when an attribute data ready event is sent to the client. It contains the following public fields:

- `device` : (`DeviceProxy`) The DeviceProxy object on which the call was executed
- `attr_name` : (`str`) The attribute name
- `event` : (`str`) The event name
- `attr_data_type` : (`int`) The attribute data type
- `ctr` : (`int`) The user counter. Set to 0 if not defined when sent by the server
- `err` : (`bool`) A boolean flag set to true if the request failed. False otherwise
- `errors` : (sequence<`DevError`>) The error stack

- `reception_date`: (*TimeVal*)

New in PyTango 7.0.0

5.2.10 History classes

class `tango.DeviceAttributeHistory`

See *DeviceAttribute*.

class `tango.DeviceDataHistory`

See *DeviceData*.

5.2.11 Enumerations & other classes

Enumerations

class `tango.LockerLanguage`

An enumeration representing the programming language in which the client application who locked is written.

- CPP : C++/Python language
- JAVA : Java language

New in PyTango 7.0.0

class `tango.CmdArgType`

An enumeration representing the command argument type.

- DevVoid
- DevBoolean
- DevShort
- DevLong
- DevFloat
- DevDouble
- DevUShort
- DevULong
- DevString
- DevVarCharArray
- DevVarShortArray
- DevVarLongArray
- DevVarFloatArray
- DevVarDoubleArray
- DevVarUShortArray
- DevVarULongArray
- DevVarStringArray
- DevVarLongStringArray
- DevVarDoubleStringArray
- DevState
- ConstDevString
- DevVarBooleanArray
- DevUChar
- DevLong64
- DevULong64
- DevVarLong64Array
- DevVarULong64Array
- DevInt
- DevEncoded
- DevEnum
- DevPipeBlob

class tango.**MessBoxType**

An enumeration representing the MessBoxType

- STOP
- INFO

New in PyTango 7.0.0

class tango.**PollObjType**

An enumeration representing the PollObjType

- POLL_CMD
- POLL_ATTR
- EVENT_HEARTBEAT
- STORE_SUBDEV

New in PyTango 7.0.0

class tango.**PollCmdCode**

An enumeration representing the PollCmdCode

- POLL_ADD_OBJ
- POLL_REM_OBJ
- POLL_START
- POLL_STOP
- POLL_UPD_PERIOD
- POLL_REM_DEV
- POLL_EXIT
- POLL_REM_EXT_TRIG_OBJ
- POLL_ADD_HEARTBEAT
- POLL_REM_HEARTBEAT

New in PyTango 7.0.0

class tango.**SerialModel**

An enumeration representing the type of serialization performed by the device server

- BY_DEVICE
- BY_CLASS
- BY_PROCESS
- NO_SYNC

class tango.**AttReqType**

An enumeration representing the type of attribute request

- READ_REQ
- WRITE_REQ

class tango.**LockCmdCode**

An enumeration representing the LockCmdCode

- LOCK_ADD_DEV
- LOCK_REM_DEV
- LOCK_UNLOCK_ALL_EXIT
- LOCK_EXIT

New in PyTango 7.0.0

class tango.**LogLevel**

An enumeration representing the LogLevel

- LOG_OFF
- LOG_FATAL
- LOG_ERROR
- LOG_WARN
- LOG_INFO
- LOG_DEBUG

New in PyTango 7.0.0

class tango.**LogTarget**

An enumeration representing the LogTarget

- LOG_CONSOLE
- LOG_FILE

- LOG_DEVICE

New in PyTango 7.0.0

class tango.**EventType**

An enumeration representing event type

- CHANGE_EVENT
- QUALITY_EVENT
- PERIODIC_EVENT
- ARCHIVE_EVENT
- USER_EVENT
- ATTR_CONF_EVENT
- DATA_READY_EVENT
- INTERFACE_CHANGE_EVENT
- PIPE_EVENT

DATA_READY_EVENT - New in PyTango 7.0.0 INTERFACE_CHANGE_EVENT - New in PyTango 9.2.2 PIPE_EVENT - New in PyTango 9.2.2

class tango.**KeepAliveCmdCode**

An enumeration representing the KeepAliveCmdCode

- EXIT_TH

New in PyTango 7.0.0

class tango.**AccessControlType**

An enumeration representing the AccessControlType

- ACCESS_READ
- ACCESS_WRITE

New in PyTango 7.0.0

class tango.**asyn_req_type**

An enumeration representing the asynchronous request type

- POLLING
- CALLBACK
- ALL_ASYNC

class tango.**cb_sub_model**

An enumeration representing callback sub model

- PUSH_CALLBACK
- PULL_CALLBACK

class tango.**AttrQuality**

An enumeration representing the attribute quality

- ATTR_VALID
- ATTR_INVALID
- ATTR_ALARM
- ATTR_CHANGING
- ATTR_WARNING

class tango.**AttrWriteType**

An enumeration representing the attribute type

- READ
- READ_WITH_WRITE
- WRITE
- READ_WRITE

class tango.**AttrDataFormat**

An enumeration representing the attribute format

- SCALAR
- SPECTRUM

- IMAGE
- FMT_UNKNOWN

class `tango.PipeWriteType`

An enumeration representing the pipe type

- PIPE_READ
- PIPE_READ_WRITE

class `tango.DevSource`

An enumeration representing the device source for data

- DEV
- CACHE
- CACHE_DEV

class `tango.ErrSeverity`

An enumeration representing the error severity

- WARN
- ERR
- PANIC

class `tango.DevState`

An enumeration representing the device state

- ON
- OFF
- CLOSE
- OPEN
- INSERT
- EXTRACT
- MOVING
- STANDBY
- FAULT
- INIT
- RUNNING
- ALARM
- DISABLE
- UNKNOWN

class `tango.DispLevel`

An enumeration representing the display level

- OPERATOR
- EXPERT

class `tango.GreenMode`

An enumeration representing the GreenMode

- Synchronous
- Futures
- Gevent

New in PyTango 8.1.0

Other classes

class `tango.Release`

Summarize release information as class attributes.

Release information:

- `name`: (`str`) package name
- `version_info`: (`tuple`) The five components of the version number: major, minor, micro, releaselevel, and serial.
- `version`: (`str`) package version in format <major>.<minor>.<micro>

- `release`: (`str`) pre-release, post-release or development release; it is empty for final releases.
- `version_long`: (`str`) package version in format `<major>.<minor>.<micro><releaselevel><serial>`
- `version_description`: (`str`) short description for the current version
- `version_number`: (`int`) `<major>*100 + <minor>*10 + <micro>`
- `description`: (`str`) package description
- `long_description`: (`str`) longer package description
- `authors`: (`dict<str(last name), tuple<str(full name),str(email)>>`) package authors
- `url`: (`str`) package url
- `download_url`: (`str`) package download url
- `platform`: (`seq`) list of available platforms
- `keywords`: (`seq`) list of keywords
- `license`: (`str`) the license

class `tango.TimeVal`

Time value structure with the following members:

- `tv_sec`: seconds
- `tv_usec`: microseconds
- `tv_nsec`: nanoseconds

isoformat (`self, sep='T'`) → `str`

Returns a string in ISO 8601 format, `YYYY-MM-DDTHH:MM:SS[.mmmmmm][+HH:MM]`

Parameters `sep`: (`str`) `sep` is used to separate the year from the time, and defaults to `'T'`

Return (`str`) a string representing the time according to a format specification.

New in version 7.1.0.

New in version 7.1.2: Documented

Changed in version 7.1.2: The `sep` parameter is not mandatory anymore and defaults to `'T'` (same as `datetime.datetime.isoformat()`)

strftime (`self, format`) → `str`

Convert a time value to a string according to a format specification.

Parameters `format`: (`str`) See the python library reference manual for formatting codes

Return (`str`) a string representing the time according to a format specification.

New in version 7.1.0.

New in version 7.1.2: Documented

totdatetime (`self`) → `datetime.datetime`

Returns a `datetime.datetime` object representing the same time value

Parameters None

Return (`datetime.datetime`) the time value in datetime format

New in version 7.1.0.

`totime (self) → float`

Returns a float representing this time value

Parameters None

Return a float representing the time value

New in version 7.1.0.

5.3 Server API

5.3.1 High level server API

Server helper classes for writing Tango device servers.

- `Device`
- `attribute`
- `command`
- `pipe`
- `device_property`
- `class_property`
- `run()`
- `server_run()`

This module provides a high level device server API. It implements *TEPI*. It exposes an easier API for developing a Tango device server.

Here is a simple example on how to write a *Clock* device server using the high level API:

```
import time
from tango.server import run
from tango.server import Device
from tango.server import attribute, command

class Clock(Device):

    time = attribute()

    def read_time(self):
        return time.time()

    @command(din_type=str, dout_type=str)
    def strftime(self, format):
        return time.strftime(format)

if __name__ == "__main__":
    run((Clock,))
```

Here is a more complete example on how to write a *PowerSupply* device server using the high level API. The example contains:

1. a read-only double scalar attribute called *voltage*
2. a read/write double scalar expert attribute *current*
3. a read-only double image attribute called *noise*
4. a *ramp* command
5. a *host* device property

6. a *port* class property

```

1 from time import time
2 from numpy.random import random_sample
3
4 from tango import AttrQuality, AttrWriteType, DispLevel
5 from tango.server import Device, attribute, command
6 from tango.server import class_property, device_property
7
8 class PowerSupply(Device):
9
10     voltage = attribute()
11
12     current = attribute(label="Current", dtype=float,
13                        display_level=DispLevel.EXPERT,
14                        access=AttrWriteType.READ_WRITE,
15                        unit="A", format="8.4f",
16                        min_value=0.0, max_value=8.5,
17                        min_alarm=0.1, max_alarm=8.4,
18                        min_warning=0.5, max_warning=8.0,
19                        fget="get_current", fset="set_current",
20                        doc="the power supply current")
21
22     noise = attribute(label="Noise", dtype=((float,)),
23                      max_dim_x=1024, max_dim_y=1024,
24                      fget="get_noise")
25
26     host = device_property(dtype=str)
27     port = class_property(dtype=int, default_value=9788)
28
29     def read_voltage(self):
30         self.info_stream("get voltage(%s, %d)" % (self.host, self.port))
31         return 10.0
32
33     def get_current(self):
34         return 2.3456, time(), AttrQuality.ATTR_WARNING
35
36     def set_current(self, current):
37         print("Current set to %f" % current)
38
39     def get_noise(self):
40         return random_sample((1024, 1024))
41
42     @command(dtype_in=float)
43     def ramp(self, value):
44         print("Ramping up...")
45
46 if __name__ == "__main__":
47     PowerSupply.run_server()

```

Pretty cool, uh?

Data types

When declaring attributes, properties or commands, one of the most important information is the data type. It is given by the keyword argument *dtype*. In order to provide a more *pythonic* interface, this argument is not restricted to the *CmdArgType* options.

For example, to define a *SCALAR* `DevLong` attribute you have several possibilities:

1. `int`
2. `'int'`
3. `'int64'`
4. `tango.CmdArgType.DevLong64`
5. `'DevLong64'`
6. `numpy.int64`

To define a *SPECTRUM* attribute simply wrap the scalar data type in any python sequence:

- using a *tuple*: `(:obj:`int`,)` or
- using a *list*: `[:obj:`int`]` or
- any other sequence type

To define an *IMAGE* attribute simply wrap the scalar data type in any python sequence of sequences:

- using a *tuple*: `((:obj:`int`,),)` or
- using a *list*: `[[:obj:`int`]]` or
- any other sequence type

Below is the complete table of equivalences.

dtype argument	converts to tango type
None	DevVoid
'None'	DevVoid
DevVoid	DevVoid
'DevVoid'	DevVoid
DevState	DevState
'DevState'	DevState
<code>bool</code>	DevBoolean
'bool'	DevBoolean
'boolean'	DevBoolean
DevBoolean	DevBoolean
'DevBoolean'	DevBoolean
<code>numpy.bool_</code>	DevBoolean
'char'	DevUChar
'chr'	DevUChar
'byte'	DevUChar
<code>chr</code>	DevUChar
DevUChar	DevUChar
'DevUChar'	DevUChar
<code>numpy.uint8</code>	DevUChar
'int16'	DevShort
DevShort	DevShort
'DevShort'	DevShort
<code>numpy.int16</code>	DevShort
'uint16'	DevUShort
DevUShort	DevUShort

continues on next page

Table 2 – continued from previous page

dtype argument	converts to tango type
'DevUShort'	DevUShort
numpy.uint16	DevUShort
'int32'	DevLong
DevLong	DevLong
'DevLong'	DevLong
numpy.int32	DevLong
'uint32'	DevULong
DevULong	DevULong
'DevULong'	DevULong
numpy.uint32	DevULong
int	DevLong64
'int'	DevLong64
'int64'	DevLong64
DevLong64	DevLong64
'DevLong64'	DevLong64
numpy.int64	DevLong64
'uint'	DevULong64
'uint64'	DevULong64
DevULong64	DevULong64
'DevULong64'	DevULong64
numpy.uint64	DevULong64
DevInt	DevInt
'DevInt'	DevInt
'float32'	DevFloat
DevFloat	DevFloat
'DevFloat'	DevFloat
numpy.float32	DevFloat
float	DevDouble
'double'	DevDouble
'float'	DevDouble
'float64'	DevDouble
DevDouble	DevDouble
'DevDouble'	DevDouble
numpy.float64	DevDouble
str	DevString
'str'	DevString
'string'	DevString
'text'	DevString
DevString	DevString
'DevString'	DevString
bytearray	DevEncoded
'bytearray'	DevEncoded
'bytes'	DevEncoded
DevEncoded	DevEncoded
'DevEncoded'	DevEncoded
DevVarBooleanArray	DevVarBooleanArray
'DevVarBooleanArray'	DevVarBooleanArray
DevVarCharArray	DevVarCharArray
'DevVarCharArray'	DevVarCharArray
DevVarShortArray	DevVarShortArray
'DevVarShortArray'	DevVarShortArray
DevVarLongArray	DevVarLongArray
'DevVarLongArray'	DevVarLongArray

continues on next page

Table 2 – continued from previous page

dtype argument	converts to tango type
DevVarLong64Array	DevVarLong64Array
'DevVarLong64Array'	DevVarLong64Array
DevVarULong64Array	DevVarULong64Array
'DevVarULong64Array'	DevVarULong64Array
DevVarFloatArray	DevVarFloatArray
'DevVarFloatArray'	DevVarFloatArray
DevVarDoubleArray	DevVarDoubleArray
'DevVarDoubleArray'	DevVarDoubleArray
DevVarUShortArray	DevVarUShortArray
'DevVarUShortArray'	DevVarUShortArray
DevVarULongArray	DevVarULongArray
'DevVarULongArray'	DevVarULongArray
DevVarStringArray	DevVarStringArray
'DevVarStringArray'	DevVarStringArray
DevVarLongStringArray	DevVarLongStringArray
'DevVarLongStringArray'	DevVarLongStringArray
DevVarDoubleStringArray	DevVarDoubleStringArray
'DevVarDoubleStringArray'	DevVarDoubleStringArray
DevPipeBlob	DevPipeBlob
'DevPipeBlob'	DevPipeBlob

class tango.server.Device (*cl, name*)

Bases: tango.server.BaseDevice

Device class for the high-level API.

All device specific classes should inherit from this class.

add_attribute (*self, attr, r_meth=None, w_meth=None, is_allo_meth=None*) → Attr

Add a new attribute to the device attribute list. Please, note that if you add an attribute to a device at device creation time, this attribute will be added to the device class attribute list. Therefore, all devices belonging to the same class created after this attribute addition will also have this attribute.

Parameters

attr (Attr or AttrData) the new attribute to be added to the list.

r_meth (callable) the read method to be called on a read request

w_meth (callable) the write method to be called on a write request (if attr is writable)

is_allo_meth (callable) the method that is called to check if it is possible to access the attribute or not

Return (Attr) the newly created attribute.

Throws DevFailed

add_command (*self, cmd, level=TANGO::OPERATOR*) → cmd

Add a new command to the device command list.

Parameters

cmd the new command to be added to the list

device_level Set this flag to true if the command must be added for only this device

Return Command

Throws DevFailed

always_executed_hook ()

Tango always_executed_hook. Default implementation does nothing

append_status (*self*, *status*, *new_line=False*) → None

Appends a string to the device status.

Parameters *status* : (str) the string to be appened to the device status
new_line : (bool) If true, appends a new line character before the string. Default is False

Return None

check_command_exists (*self*) → None

This method check that a command is supported by the device and does not need input value. The method throws an exception if the command is not defined or needs an input value

Parameters

cmd_name (str) the command name

Return None

Throws DevFailed API_IncompatibleCmdArgumentType,
 API_CommandNotFound

New in PyTango 7.1.2

debug_stream (*self*, *msg*, **args*) → None

Sends the given message to the tango debug stream.

Since PyTango 7.1.3, the same can be achieved with:

```
print(msg, file=self.log_debug)
```

Parameters

msg (str) the message to be sent to the debug stream

Return None

delete_device (*self*) → None

Delete the device.

Parameters None

Return None

error_stream (*self*, *msg*, **args*) → None

Sends the given message to the tango error stream.

Since PyTango 7.1.3, the same can be achieved with:

```
print(msg, file=self.log_error)
```

Parameters

msg (str) the message to be sent to the error stream

Return None

fatal_stream (*self*, *msg*, **args*) → None

Sends the given message to the tango fatal stream.

Since PyTango 7.1.3, the same can be achieved with:

```
print(msg, file=self.log_fatal)
```

Parameters

msg (*str*) the message to be sent to the fatal stream

Return None

get_attr_min_poll_period (*self*) → seq<str>

Returns the min attribute poll period

Parameters None

Return (*seq*) the min attribute poll period

New in PyTango 7.2.0

get_attr_poll_ring_depth (*self*, *attr_name*) → int

Returns the attribute poll ring depth

Parameters

attr_name (*str*) the attribute name

Return (*int*) the attribute poll ring depth

New in PyTango 7.1.2

get_attribute_poll_period (*self*, *attr_name*) → int

Returns the attribute polling period (ms) or 0 if the attribute is not polled.

Parameters

attr_name (*str*) attribute name

Return (*int*) attribute polling period (ms) or 0 if it is not polled

New in PyTango 8.0.0

get_cmd_min_poll_period (*self*) → seq<str>

Returns the min command poll period

Parameters None

Return (*seq*) the min command poll period

New in PyTango 7.2.0

get_cmd_poll_ring_depth (*self*, *cmd_name*) → int

Returns the command poll ring depth

Parameters

cmd_name (*str*) the command name

Return (*int*) the command poll ring depth

New in PyTango 7.1.2

get_command_poll_period(*self*, *cmd_name*) → int

Returns the command polling period (ms) or 0 if the command is not polled.

Parameters

cmd_name (str) command name

Return (int) command polling period (ms) or 0 if it is not polled

New in PyTango 8.0.0

get_dev_idl_version(*self*) → int

Returns the IDL version

Parameters None

Return (int) the IDL version

New in PyTango 7.1.2

get_device_attr(*self*) → MultiAttribute

Get device multi attribute object.

Parameters None

Return (MultiAttribute) the device's MultiAttribute object

get_device_properties(*self*, *ds_class=None*) → None

Utility method that fetches all the device properties from the database and converts them into members of this DeviceImpl.

Parameters

ds_class (DeviceClass) the DeviceClass object. Optional. Default value is None meaning that the corresponding DeviceClass object for this DeviceImpl will be used

Return None

Throws DevFailed

get_exported_flag(*self*) → bool

Returns the state of the exported flag

Parameters None

Return (bool) the state of the exported flag

New in PyTango 7.1.2

get_logger(*self*) → Logger

Returns the Logger object for this device

Parameters None

Return (Logger) the Logger object for this device

get_min_poll_period(*self*) → int

Returns the min poll period

Parameters None

Return (`int`) the min poll period

New in PyTango 7.2.0

get_name (*self*)

Get a COPY of the device name.

Parameters None

Return (`str`) the device name

get_non_auto_polled_attr (*self*) → sequence<str>

Returns a COPY of the list of non automatic polled attributes

Parameters None

Return (sequence<str>) a COPY of the list of non automatic polled attributes

New in PyTango 7.1.2

get_non_auto_polled_cmd (*self*) → sequence<str>

Returns a COPY of the list of non automatic polled commands

Parameters None

Return (sequence<str>) a COPY of the list of non automatic polled commands

New in PyTango 7.1.2

get_poll_old_factor (*self*) → `int`

Returns the poll old factor

Parameters None

Return (`int`) the poll old factor

New in PyTango 7.1.2

get_poll_ring_depth (*self*) → `int`

Returns the poll ring depth

Parameters None

Return (`int`) the poll ring depth

New in PyTango 7.1.2

get_polled_attr (*self*) → sequence<str>

Returns a COPY of the list of polled attributes

Parameters None

Return (sequence<str>) a COPY of the list of polled attributes

New in PyTango 7.1.2

get_polled_cmd (*self*) → sequence<str>

Returns a COPY of the list of polled commands

Parameters None

Return (sequence<str>) a COPY of the list of polled commands

New in PyTango 7.1.2

get_prev_state (*self*) → DevState

Get a COPY of the device's previous state.

Parameters None

Return (DevState) the device's previous state

get_state (*self*) → DevState

Get a COPY of the device state.

Parameters None

Return (DevState) Current device state

get_status (*self*) → str

Get a COPY of the device status.

Parameters None

Return (str) the device status

info_stream (*self*, *msg*, **args*) → None

Sends the given message to the tango info stream.

Since PyTango 7.1.3, the same can be achieved with:

```
print(msg, file=self.log_info)
```

Parameters

msg (str) the message to be sent to the info stream

Return None

init_device ()

Tango init_device method. Default implementation calls *get_device_properties* ()

initialize_dynamic_attributes ()

Method executed at initialization phase to create dynamic attributes. Default implementation does nothing. Overwrite when necessary.

is_device_locked (*self*) → bool

Returns if this device is locked by a client

Parameters None

Return (bool) True if it is locked or False otherwise

New in PyTango 7.1.2

is_polled (*self*) → bool

Returns if it is polled

Parameters None

Return (`bool`) True if it is polled or False otherwise

New in PyTango 7.1.2

is_there_subscriber (*self*, *att_name*, *event_type*) → `bool`

Check if there is subscriber(s) listening for the event.

This method returns a boolean set to true if there are some subscriber(s) listening on the event specified by the two method arguments. Be aware that there is some delay (up to 600 sec) between this method returning false and the last subscriber unsubscription or crash...

The device interface change event is not supported by this method.

Parameters

att_name (`str`) the attribute name

event_type (`EventType`) the event type

Return True if there is at least one listener or False otherwise

push_archive_event (*self*, *attr_name*) → `None`

push_archive_event (*self*, *attr_name*, *except*) → `None`

push_archive_event (*self*, *attr_name*, *data*, *dim_x* = 1, *dim_y* = 0) → `None`

push_archive_event (*self*, *attr_name*, *str_data*, *data*) → `None`

push_archive_event (*self*, *attr_name*, *data*, *time_stamp*, *quality*, *dim_x* = 1, *dim_y* = 0) → `None`

push_archive_event (*self*, *attr_name*, *str_data*, *data*, *time_stamp*, *quality*) → `None`

Push an archive event for the given attribute name. The event is pushed to the notification daemon.

Parameters

attr_name (`str`) attribute name

data the data to be sent as attribute event data. Data must be compatible with the attribute type and format. for SPECTRUM and IMAGE attributes, data can be any type of sequence of elements compatible with the attribute type

str_data (`str`) special variation for DevEncoded data type. In this case 'data' must be a str or an object with the buffer interface.

except (`DevFailed`) Instead of data, you may want to send an exception.

dim_x (`int`) the attribute x length. Default value is 1

dim_y (`int`) the attribute y length. Default value is 0

time_stamp (`double`) the time stamp

quality (`AttrQuality`) the attribute quality factor

Throws `DevFailed` If the attribute data type is not coherent.

push_att_conf_event (*self*, *attr*) → `None`

Push an attribute configuration event.

Parameters (Attribute) the attribute for which the configuration event will be sent.

Return None

New in PyTango 7.2.1

push_change_event (*self*, *attr_name*) → None

push_change_event (*self*, *attr_name*, *except*) → None

push_change_event (*self*, *attr_name*, *data*, *dim_x* = 1, *dim_y* = 0) → None

push_change_event (*self*, *attr_name*, *str_data*, *data*) → None

push_change_event (*self*, *attr_name*, *data*, *time_stamp*, *quality*, *dim_x* = 1, *dim_y* = 0) → None

push_change_event (*self*, *attr_name*, *str_data*, *data*, *time_stamp*, *quality*) → None

Push a change event for the given attribute name. The event is pushed to the notification daemon.

Parameters

attr_name (*str*) attribute name

data the data to be sent as attribute event data. Data must be compatible with the attribute type and format. for SPECTRUM and IMAGE attributes, data can be any type of sequence of elements compatible with the attribute type

str_data (*str*) special variation for DevEncoded data type. In this case 'data' must be a str or an object with the buffer interface.

except (*DevFailed*) Instead of data, you may want to send an exception.

dim_x (*int*) the attribute x length. Default value is 1

dim_y (*int*) the attribute y length. Default value is 0

time_stamp (*double*) the time stamp

quality (*AttrQuality*) the attribute quality factor

Throws *DevFailed* If the attribute data type is not coherent.

push_data_ready_event (*self*, *attr_name*, *counter*=0) → None

Push a data ready event for the given attribute name. The event is pushed to the notification daemon.

The method needs only the attribute name and an optional "counter" which will be passed unchanged within the event

Parameters

attr_name (*str*) attribute name

counter (*int*) the user counter

Return None

Throws *DevFailed* If the attribute name is unknown.

push_event (*self*, *attr_name*, *filt_names*, *filt_vals*) → None

push_event (*self*, *attr_name*, *filt_names*, *filt_vals*, *data*, *dim_x* = 1, *dim_y* = 0) → None

push_event (*self*, *attr_name*, *filt_names*, *filt_vals*, *str_data*, *data*) → None

push_event (*self*, *attr_name*, *filt_names*, *filt_vals*, *data*, *time_stamp*, *quality*, *dim_x* = 1, *dim_y* = 0) -> None

push_event (*self*, *attr_name*, *filt_names*, *filt_vals*, *str_data*, *data*, *time_stamp*, *quality*) -> None

Push a user event for the given attribute name. The event is pushed to the notification daemon.

Parameters

attr_name (*str*) attribute name

filt_names (sequence<*str*>) the filterable fields name

filt_vals (sequence<*double*>) the filterable fields value

data the data to be sent as attribute event data. Data must be compatible with the attribute type and format. for SPECTRUM and IMAGE attributes, data can be any type of sequence of elements compatible with the attribute type

str_data (*str*) special variation for DevEncoded data type. In this case 'data' must be a str or an object with the buffer interface.

dim_x (*int*) the attribute x length. Default value is 1

dim_y (*int*) the attribute y length. Default value is 0

time_stamp (*double*) the time stamp

quality (*AttrQuality*) the attribute quality factor

Throws DevFailed If the attribute data type is not coherent.

push_pipe_event (*self*, *blob*) → None

Push an pipe event.

Parameters the blob which pipe event will be send.

Return None

New in PyTango 9.2.2

register_signal (*self*, *signo*) → None

Register a signal. Register this device as device to be informed when signal signo is sent to to the device server process

Parameters

signo (*int*) signal identifier

Return None

remove_attribute (*self*, *attr_name*) → None

Remove one attribute from the device attribute list.

Parameters

attr_name (*str*) attribute name

Return None

Throws DevFailed

remove_command (*self*, *attr_name*) → *None*

Remove one command from the device command list.

Parameters

cmd_name (*str*) command name to be removed from the list

free_it Boolean set to true if the command object must be freed.

clean_db Clean command related information (included polling info if the command is polled) from database.

Return *None*

Throws *DevFailed*

classmethod run_server (*args=None*, ***kwargs*)

Run the class as a device server. It is based on the `tango.server.run` method.

The difference is that the device class and server name are automatically given.

Args:

args (iterable): args as given in the `tango.server.run` method without the server name. If *None*, the `sys.argv` list is used

kwargs: the other keywords argument are as given in the `tango.server.run` method.

set_archive_event (*self*, *attr_name*, *implemented*, *detect=True*) → *None*

Set an implemented flag for the attribute to indicate that the server fires archive events manually, without the polling to be started. If the `detect` parameter is set to true, the criteria specified for the archive event are verified and the event is only pushed if they are fulfilled. If `detect` is set to false the event is fired without any value checking!

Parameters

attr_name (*str*) attribute name

implemented (*bool*) True when the server fires change events manually.

detect (*bool*) Triggers the verification of the change event properties when set to true. Default value is true.

Return *None*

set_change_event (*self*, *attr_name*, *implemented*, *detect=True*) → *None*

Set an implemented flag for the attribute to indicate that the server fires change events manually, without the polling to be started. If the `detect` parameter is set to true, the criteria specified for the change event are verified and the event is only pushed if they are fulfilled. If `detect` is set to false the event is fired without any value checking!

Parameters

attr_name (*str*) attribute name

implemented (*bool*) True when the server fires change events manually.

detect (*bool*) Triggers the verification of the change event properties when set to true. Default value is true.

Return *None*

set_state (*self*, *new_state*) → None

Set device state.

Parameters

new_state (`DevState`) the new device state

Return None

set_status (*self*, *new_status*) → None

Set device status.

Parameters

new_status (`str`) the new device status

Return None

signal_handler (*self*, *signo*) → None

Signal handler. The method executed when the signal arrived in the device server process. This method is defined as virtual and then, can be redefined following device needs.

Parameters

signo (`int`) the signal number

Return None

Throws `DevFailed` This method does not throw exception but a redefined method can.

stop_polling (*self*) → None

stop_polling (*self*, *with_db_upd*) → None

Stop all polling for a device. if the device is polled, call this method before deleting it.

Parameters

with_db_upd (`bool`) Is it necessary to update db ?

Return None

New in PyTango 7.1.2

unregister_signal (*self*, *signo*) → None

Unregister a signal. Unregister this device as device to be informed when signal signo is sent to to the device server process

Parameters

signo (`int`) signal identifier

Return None

warn_stream (*self*, *msg*, **args*) → None

Sends the given message to the tango warn stream.

Since PyTango 7.1.3, the same can be achieved with:

```
print(msg, file=self.log_warn)
```

Parameters

msg (*str*) the message to be sent to the warn stream

Return None

write_attr_hardware (*self*) → None

Write the hardware for attributes. Default method to implement an action necessary on a device to write the hardware involved in a write attribute. This method must be redefined in sub-classes in order to support writable attribute

Parameters

attr_list [(sequence<int>) list of indices in the device object attribute vector] of an attribute to be written.

Return None

Throws DevFailed This method does not throw exception but a redefined method can.

class tango.server.attribute (*fget=None, **kwargs*)

Declares a new tango attribute in a *Device*. To be used like the python native `property` function. For example, to declare a scalar, *tango.DevDouble*, read-only attribute called *voltage* in a *PowerSupply Device* do:

```
class PowerSupply(Device):

    voltage = attribute()

    def read_voltage(self):
        return 999.999
```

The same can be achieved with:

```
class PowerSupply(Device):

    @attribute
    def voltage(self):
        return 999.999
```

It receives multiple keyword arguments.

parameter	type	default value	description
name	<i>str</i>	class member name	alternative attribute name
dtype	<i>object</i>	DevDouble	data type (see <i>Data type equivalence</i>)
dformat	<i>AttrDataFormat</i>	SCALAR	data format
max_dim_x	<i>int</i>	1	maximum size for x dimension (ignored for
max_dim_y	<i>int</i>	0	maximum size for y dimension (ignored for
display_level	<i>DispLevel</i>	OPERATOR	display level
polling_period	<i>int</i>	-1	polling period
memorized	<i>bool</i>	False	attribute should or not be memorized
hw_memorized	<i>bool</i>	False	write method should be called at startup wh
access	<i>AttrWriteType</i>	READ	read only / read write / write only access
fget (or fread)	<i>str</i> or callable	'read_<attr_name>'	read method name or method object
fset (or fwrite)	<i>str</i> or callable	'write_<attr_name>'	write method name or method object
fisallowed	<i>str</i> or callable	'is_<attr_name>_allowed'	is allowed method name or method object
label	<i>str</i>	'<attr_name>'	attribute label
enum_labels	sequence	None	the list of enumeration labels (enum data ty
doc (or description)	<i>str</i>	"	attribute description

Table 3 – continued from previous page

parameter	type	default value	description
unit	str	''	physical units the attribute value is in
standard_unit	str	''	physical standard unit
display_unit	str	''	physical display unit (hint for clients)
format	str	'6.2f'	attribute representation format
min_value	str	None	minimum allowed value
max_value	str	None	maximum allowed value
min_alarm	str	None	minimum value to trigger attribute alarm
max_alarm	str	None	maximum value to trigger attribute alarm
min_warning	str	None	minimum value to trigger attribute warning
max_warning	str	None	maximum value to trigger attribute warning
delta_val	str	None	
delta_t	str	None	
abs_change	str	None	minimum value change between events that
rel_change	str	None	minimum relative change between events th
period	str	None	
archive_abs_change	str	None	
archive_rel_change	str	None	
archive_period	str	None	
green_mode	GreenMode	None	green mode for read and write. None means
read_green_mode	GreenMode	None	green mode for read. None means use serve
write_green_mode	GreenMode	None	green mode for write. None means use serv
forwarded	bool	False	the attribute should be forwarded if True

Note: avoid using *dformat* parameter. If you need a SPECTRUM attribute of say, boolean type, use instead `dtype=(bool,)`.

Example of a integer writable attribute with a customized label, unit and description:

```
class PowerSupply(Device):

    current = attribute(label="Current", unit="mA", dtype=int,
                       access=AttrWriteType.READ_WRITE,
                       doc="the power supply current")

    def init_device(self):
        Device.init_device(self)
        self._current = -1

    def read_current(self):
        return self._current

    def write_current(self, current):
        self._current = current
```

The same, but using attribute as a decorator:

```
class PowerSupply(Device):

    def init_device(self):
        Device.init_device(self)
        self._current = -1

    @attribute(label="Current", unit="mA", dtype=int)
    def current(self):
        """the power supply current"""
```

(continues on next page)

(continued from previous page)

```

    return 999.999

@current.write
def current(self, current):
    self._current = current

```

In this second format, defining the *write* implicitly sets the attribute access to READ_WRITE.

New in version 8.1.7: added `green_mode`, `read_green_mode` and `write_green_mode` options

```

tango.server.command(f=None, dtype_in=None, dformat_in=None, doc_in='',
                    dtype_out=None, dformat_out=None, doc_out='', display_level=None,
                    polling_period=None, green_mode=None)

```

Declares a new tango command in a *Device*. To be used like a decorator in the methods you want to declare as tango commands. The following example declares commands:

- *void TurnOn(void)*
- *void Ramp(DevDouble current)*
- *DevBool Pressurize(DevDouble pressure)*

```

class PowerSupply(Device):

    @command
    def TurnOn(self):
        self.info_stream('Turning on the power supply')

    @command(dtype_in=float)
    def Ramp(self, current):
        self.info_stream('Ramping on %f...' % current)

    @command(dtype_in=float, doc_in='the pressure to be set',
            dtype_out=bool, doc_out='True if it worked, False otherwise')
    def Pressurize(self, pressure):
        self.info_stream('Pressurizing to %f...' % pressure)
        return True

```

Note: avoid using *dformat* parameter. If you need a SPECTRUM attribute of say, boolean type, use instead `dtype=(bool,)`.

Parameters

- **dtype_in** – a *data type* describing the type of parameter. Default is None meaning no parameter.
- **dformat_in** (*AttrDataFormat*) – parameter data format. Default is None.
- **doc_in** (*str*) – parameter documentation
- **dtype_out** – a *data type* describing the type of return value. Default is None meaning no return value.
- **dformat_out** (*AttrDataFormat*) – return value data format. Default is None.
- **doc_out** (*str*) – return value documentation
- **display_level** (*DispLevel*) – display level for the command (optional)
- **polling_period** (*int*) – polling period in milliseconds (optional)
- **green_mode** – set green mode on this specific command. Default value is None meaning use the server green mode. Set it to `Green-Mode.Synchronous` to force a non green command in a green server.

New in version 8.1.7: added `green_mode` option

New in version 9.2.0: added `display_level` and `polling_period` optional argument

class `tango.server.pipe` (*fget=None, **kwargs*)

Declares a new tango pipe in a *Device*. To be used like the python native `property` function.

Checkout the *pipe data types* to see what you should return on a pipe read request and what to expect as argument on a pipe write request.

For example, to declare a read-only pipe called *ROI* (for Region Of Interest), in a *Detector Device* do:

```
class Detector(Device):

    ROI = pipe()

    def read_ROI(self):
        return ('ROI', ({'name': 'x', 'value': 0},
                        {'name': 'y', 'value': 10},
                        {'name': 'width', 'value': 100},
                        {'name': 'height', 'value': 200}))
```

The same can be achieved with (also showing that a dict can be used to pass blob data):

```
class Detector(Device):

    @pipe
    def ROI(self):
        return 'ROI', dict(x=0, y=10, width=100, height=200)
```

It receives multiple keyword arguments.

parameter	type	default value	description
name	str	class member name	alternative pipe name
display_level	<i>DispLevel</i>	OPERATOR	display level
access	<i>PipeWriteType</i>	READ	read only/ read write access
fget (or fread)	str or callable	'read_<pipe_name>'	read method name or method object
fset (or fwrite)	str or callable	'write_<pipe_name>'	write method name or method object
isallowed	str or callable	'is_<pipe_name>_allowed'	allowed method name or method object
label	str	'<pipe_name>'	pipe label
doc (or description)	str	''	pipe description
green_mode	<i>GreenMode</i>	None	green mode for read and write. None means use server green mode.
read_green_mode	<i>GreenMode</i>	None	green mode for read. None means use server green mode.
write_green_mode	<i>GreenMode</i>	None	green mode for write. None means use server green mode.

The same example with a read-write ROI, a customized label and description:

```
class Detector(Device):

    ROI = pipe(label='Region Of Interest', doc='The active region of interest',
              (continues on next page)
```

(continued from previous page)

```

        access=PipeWriteType.PIPE_READ_WRITE)

    def init_device(self):
        Device.init_device(self)
        self.__roi = 'ROI', dict(x=0, y=10, width=100, height=200)

    def read_ROI(self):
        return self.__roi

    def write_ROI(self, roi):
        self.__roi = roi

```

The same, but using pipe as a decorator:

```

class Detector(Device):

    def init_device(self):
        Device.init_device(self)
        self.__roi = 'ROI', dict(x=0, y=10, width=100, height=200)

    @pipe(label="Region Of Interest")
    def ROI(self):
        """The active region of interest"""
        return self.__roi

    @ROI.write
    def ROI(self, roi):
        self.__roi = roi

```

In this second format, defining the *write* / *setter* implicitly sets the pipe access to READ_WRITE.

New in version 9.2.0.

class `tango.server.device_property` (*dtype*, *doc*='', *mandatory*=False, *default_value*=None, *update_db*=False)

Declares a new tango device property in a *Device*. To be used like the python native `property` function. For example, to declare a scalar, *tango.DevString*, device property called *host* in a *PowerSupply Device* do:

```

from tango.server import Device, DeviceMeta
from tango.server import device_property

class PowerSupply(Device):

    host = device_property(dtype=str)
    port = device_property(dtype=int, mandatory=True)

```

Parameters

- **dtype** – Data type (see *Data types*)
- **doc** – property documentation (optional)
- **(optional *mandatory*)** – default is False)
- **default_value** – default value for the property (optional)
- **update_db** (*bool*) – tells if set value should write the value to database. [default: False]

New in version 8.1.7: added `update_db` option

class `tango.server.class_property` (*dtype*, *doc*='', *default_value*=None, *update_db*=False)

Declares a new tango class property in a *Device*. To be used like the python native `property`

function. For example, to declare a scalar, *tango.DevString*, class property called *port* in a *PowerSupply Device* do:

```
from tango.server import Device, DeviceMeta
from tango.server import class_property

class PowerSupply(Device):

    port = class_property(dtype=int, default_value=9788)
```

Parameters

- **dtype** – Data type (see *Data types*)
- **doc** – property documentation (optional)
- **default_value** – default value for the property (optional)
- **update_db** (*bool*) – tells if set value should write the value to database. [default: False]

New in version 8.1.7: added `update_db` option

```
tango.server.run(classes, args=None, msg_stream=<_io.TextIOWrapper name='<stdout>'
mode='w' encoding='utf-8'>, verbose=False, util=None, event_loop=None,
post_init_callback=None, green_mode=None, raises=False)
```

Provides a simple way to run a tango server. It handles exceptions by writing a message to the `msg_stream`.

The `classes` parameter can be either a sequence of:

- `: class:~tango.server.Device` or
- a sequence of two elements *DeviceClass*, *DeviceImpl* or
- a sequence of three elements *DeviceClass*, *DeviceImpl*, tango class name (str)

or a dictionary where:

- key is the tango class name
- **value is either:**

- a `: class:~tango.server.Device` class or
- a sequence of two elements *DeviceClass*, *DeviceImpl* or
- a sequence of three elements *DeviceClass*, *DeviceImpl*, tango class name (str)

The optional `post_init_callback` can be a callable (without arguments) or a tuple where the first element is the callable, the second is a list of arguments (optional) and the third is a dictionary of keyword arguments (also optional).

Note: the order of registration of tango classes defines the order tango uses to initialize the corresponding devices. if using a dictionary as argument for classes be aware that the order of registration becomes arbitrary. If you need a predefined order use a sequence or an `OrderedDict`.

Example 1: registering and running a *PowerSupply* inheriting from *Device*:

```
from tango.server import Device, DeviceMeta, run

class PowerSupply(Device):
    pass

run((PowerSupply,))
```

Example 2: registering and running a *MyServer* defined by tango classes *MyServerClass* and *MyServer*:


```

from tango import Device_4Impl, DeviceClass
from tango.server import run

class MyServer(Device_4Impl):
    pass

class MyServerClass(DeviceClass):
    pass

run({'MyServer': (MyServerClass, MyServer)})

```

Example 3: registering and running a MyServer defined by tango classes *MyServerClass* and *MyServer*:

```

from tango import Device_4Impl, DeviceClass
from tango.server import Device, DeviceMeta, run

class PowerSupply(Device):
    pass

class MyServer(Device_4Impl):
    pass

class MyServerClass(DeviceClass):
    pass

run([PowerSupply, [MyServerClass, MyServer]])
# or: run({'MyServer': (MyServerClass, MyServer)})

```

Parameters

- **classes** (*sequence or dict*) – a sequence of *Device* classes or a dictionary where keyword is the tango class name and value is a sequence of Tango Device Class python class, and Tango Device python class
- **args** (*list*) – list of command line arguments [default: None, meaning use sys.argv]
- **msg_stream** – stream where to put messages [default: sys.stdout]
- **util** (*Util*) – PyTango Util object [default: None meaning create a Util instance]
- **event_loop** (*callable*) – event_loop callable
- **post_init_callback** (*callable or tuple (see description above)*) – an optional callback that is executed between the calls Util.server_init and Util.server_run
- **raises** (*bool*) – Disable error handling and propagate exceptions from the server

Returns The Util singleton object

Return type *Util*

New in version 8.1.2.

Changed in version 8.1.4: when classes argument is a sequence, the items can also be a sequence <TangoClass, TangoClassClass>[, tango class name]

Changed in version 9.2.2: *raises* argument has been added

```
tango.server.server_run (classes, args=None, msg_stream=<_io.TextIOWrapper
                        name='<stdout>' mode='w' encoding='utf-8'>, verbose=False,
                        util=None, event_loop=None, post_init_callback=None,
                        green_mode=None)
```

Since PyTango 8.1.2 it is just an alias to `run()`. Use `run()` instead.

New in version 8.0.0.

Changed in version 8.0.3: Added `util` keyword parameter. Returns util object

Changed in version 8.1.1: Changed default `msg_stream` from `stderr` to `stdout` Added `event_loop` keyword parameter. Returns util object

Changed in version 8.1.2: Added `post_init_callback` keyword parameter

Deprecated since version 8.1.2: Use `run()` instead.

5.3.2 Device

DeviceImpl

class `tango.LatestDeviceImpl`

Latest implementation of the TANGO device base class (alias for `Device_5Impl`).

It inherits from CORBA classes where all the network layer is implemented.

add_attribute (*self*, *attr*, *r_meth=None*, *w_meth=None*, *is_allo_meth=None*) → *Attr*

Add a new attribute to the device attribute list. Please, note that if you add an attribute to a device at device creation time, this attribute will be added to the device class attribute list. Therefore, all devices belonging to the same class created after this attribute addition will also have this attribute.

Parameters

attr (*Attr* or *AttrData*) the new attribute to be added to the list.

r_meth (*callable*) the read method to be called on a read request

w_meth (*callable*) the write method to be called on a write request (if *attr* is writable)

is_allo_meth (*callable*) the method that is called to check if it is possible to access the attribute or not

Return (*Attr*) the newly created attribute.

Throws *DevFailed*

add_command (*self*, *cmd*, *level=TANGO::OPERATOR*) → *cmd*

Add a new command to the device command list.

Parameters

cmd the new command to be added to the list

device_level Set this flag to true if the command must be added for only this device

Return *Command*

Throws *DevFailed*

always_executed_hook (*self*) → *None*

Hook method. Default method to implement an action necessary on a device before any command is executed. This method can be redefined in sub-classes in case of the default behaviour does not fulfill the needs

Parameters None

Return None

Throws *DevFailed* This method does not throw exception but a redefined method can.

append_status (*self*, *status*, *new_line=False*) → None

Appends a string to the device status.

Parameters *status* : (str) the string to be appended to the device status
new_line : (bool) If true, appends a new line character before the string. Default is False

Return None

check_command_exists (*self*) → None

This method check that a command is supported by the device and does not need input value. The method throws an exception if the command is not defined or needs an input value

Parameters

cmd_name (str) the command name

Return None

Throws *DevFailed* API_IncompatibleCmdArgumentType,
API_CommandNotFound

New in PyTango 7.1.2

debug_stream (*self*, *msg*, **args*) → None

Sends the given message to the tango debug stream.

Since PyTango 7.1.3, the same can be achieved with:

```
print(msg, file=self.log_debug)
```

Parameters

msg (str) the message to be sent to the debug stream

Return None

delete_device (*self*) → None

Delete the device.

Parameters None

Return None

dev_state (*self*) → DevState

Get device state. Default method to get device state. The behaviour of this method depends on the device state. If the device state is ON or ALARM, it reads the attribute(s) with an alarm level defined, check if the read value is above/below the alarm and eventually change the state to ALARM, return the device state. For all th other device state, this method simply returns the state This method can be redefined in sub-classes in case of the default behaviour does not fullfill the needs.

Parameters None

Return (*DevState*) the device state

Throws *DevFailed* - If it is necessary to read attribute(s) and a problem occurs during the reading

dev_status (*self*) → *str*

Get device status. Default method to get device status. It returns the contents of the device `dev_status` field. If the device state is ALARM, alarm messages are added to the device status. This method can be redefined in sub-classes in case of the default behaviour does not fullfill the needs.

Parameters None

Return (*str*) the device status

Throws *DevFailed* - If it is necessary to read attribute(s) and a problem occurs during the reading

error_stream (*self*, *msg*, **args*) → *None*

Sends the given message to the tango error stream.

Since PyTango 7.1.3, the same can be achieved with:

```
print(msg, file=self.log_error)
```

Parameters

msg (*str*) the message to be sent to the error stream

Return *None*

fatal_stream (*self*, *msg*, **args*) → *None*

Sends the given message to the tango fatal stream.

Since PyTango 7.1.3, the same can be achieved with:

```
print(msg, file=self.log_fatal)
```

Parameters

msg (*str*) the message to be sent to the fatal stream

Return *None*

get_attr_min_poll_period (*self*) → *seq*<*str*>

Returns the min attribute poll period

Parameters None

Return (*seq*) the min attribute poll period

New in PyTango 7.2.0

get_attr_poll_ring_depth (*self*, *attr_name*) → *int*

Returns the attribute poll ring depth

Parameters

attr_name (*str*) the attribute name

Return (`int`) the attribute poll ring depth

New in PyTango 7.1.2

get_attribute_poll_period(*self*, *attr_name*) → `int`

Returns the attribute polling period (ms) or 0 if the attribute is not polled.

Parameters

attr_name (`str`) attribute name

Return (`int`) attribute polling period (ms) or 0 if it is not polled

New in PyTango 8.0.0

get_cmd_min_poll_period(*self*) → `seq<str>`

Returns the min command poll period

Parameters None

Return (`seq`) the min command poll period

New in PyTango 7.2.0

get_cmd_poll_ring_depth(*self*, *cmd_name*) → `int`

Returns the command poll ring depth

Parameters

cmd_name (`str`) the command name

Return (`int`) the command poll ring depth

New in PyTango 7.1.2

get_command_poll_period(*self*, *cmd_name*) → `int`

Returns the command polling period (ms) or 0 if the command is not polled.

Parameters

cmd_name (`str`) command name

Return (`int`) command polling period (ms) or 0 if it is not polled

New in PyTango 8.0.0

get_dev_idl_version(*self*) → `int`

Returns the IDL version

Parameters None

Return (`int`) the IDL version

New in PyTango 7.1.2

get_device_attr(*self*) → `MultiAttribute`

Get device multi attribute object.

Parameters None

Return (`MultiAttribute`) the device's `MultiAttribute` object

get_device_properties(*self*, *ds_class=None*) → `None`

Utility method that fetches all the device properties from the database and converts them into members of this DeviceImpl.

Parameters

ds_class (*DeviceClass*) the DeviceClass object. Optional. Default value is None meaning that the corresponding DeviceClass object for this DeviceImpl will be used

Return None

Throws *DevFailed*

get_exported_flag (*self*) → bool

Returns the state of the exported flag

Parameters None

Return (bool) the state of the exported flag

New in PyTango 7.1.2

get_logger (*self*) → Logger

Returns the Logger object for this device

Parameters None

Return (Logger) the Logger object for this device

get_min_poll_period (*self*) → int

Returns the min poll period

Parameters None

Return (int) the min poll period

New in PyTango 7.2.0

get_name (*self*)

Get a COPY of the device name.

Parameters None

Return (str) the device name

get_non_auto_polled_attr (*self*) → sequence<str>

Returns a COPY of the list of non automatic polled attributes

Parameters None

Return (sequence<str>) a COPY of the list of non automatic polled attributes

New in PyTango 7.1.2

get_non_auto_polled_cmd (*self*) → sequence<str>

Returns a COPY of the list of non automatic polled commands

Parameters None

Return (sequence<str>) a COPY of the list of non automatic polled commands

New in PyTango 7.1.2

get_poll_old_factor (*self*) → int

Returns the poll old factor

Parameters None

Return (int) the poll old factor

New in PyTango 7.1.2

get_poll_ring_depth (*self*) → int

Returns the poll ring depth

Parameters None

Return (int) the poll ring depth

New in PyTango 7.1.2

get_polled_attr (*self*) → sequence<str>

Returns a COPY of the list of polled attributes

Parameters None

Return (sequence<str>) a COPY of the list of polled attributes

New in PyTango 7.1.2

get_polled_cmd (*self*) → sequence<str>

Returns a COPY of the list of polled commands

Parameters None

Return (sequence<str>) a COPY of the list of polled commands

New in PyTango 7.1.2

get_prev_state (*self*) → DevState

Get a COPY of the device's previous state.

Parameters None

Return (*DevState*) the device's previous state

get_state (*self*) → DevState

Get a COPY of the device state.

Parameters None

Return (*DevState*) Current device state

get_status (*self*) → str

Get a COPY of the device status.

Parameters None

Return (str) the device status

info_stream (*self*, *msg*, **args*) → None

Sends the given message to the tango info stream.

Since PyTango 7.1.3, the same can be achieved with:

```
print(msg, file=self.log_info)
```

Parameters

msg (*str*) the message to be sent to the info stream

Return None

init_device (*self*) → None

Intialize the device.

Parameters None

Return None

is_device_locked (*self*) → bool

Returns if this device is locked by a client

Parameters None

Return (bool) True if it is locked or False otherwise

New in PyTango 7.1.2

is_polled (*self*) → bool

Returns if it is polled

Parameters None

Return (bool) True if it is polled or False otherwise

New in PyTango 7.1.2

is_there_subscriber (*self, att_name, event_type*) → bool

Check if there is subscriber(s) listening for the event.

This method returns a boolean set to true if there are some subscriber(s) listening on the event specified by the two method arguments. Be aware that there is some delay (up to 600 sec) between this method returning false and the last subscriber unsubscription or crash...

The device interface change event is not supported by this method.

Parameters

att_name (*str*) the attribute name

event_type (**EventType**) the event type

Return True if there is at least one listener or False otherwise

push_archive_event (*self, attr_name*) → None

push_archive_event (*self, attr_name, except*) → None

push_archive_event (*self, attr_name, data, dim_x = 1, dim_y = 0*) → None

push_archive_event (*self, attr_name, str_data, data*) → None

push_archive_event (*self, attr_name, data, time_stamp, quality, dim_x = 1, dim_y = 0*) → None

push_archive_event (*self, attr_name, str_data, data, time_stamp, quality*) -> None

Push an archive event for the given attribute name. The event is pushed to the notification daemon.

Parameters

attr_name (*str*) attribute name

data the data to be sent as attribute event data. Data must be compatible with the attribute type and format. for SPECTRUM and IMAGE attributes, data can be any type of sequence of elements compatible with the attribute type

str_data (*str*) special variation for DevEncoded data type. In this case 'data' must be a str or an object with the buffer interface.

except (*DevFailed*) Instead of data, you may want to send an exception.

dim_x (*int*) the attribute x length. Default value is 1

dim_y (*int*) the attribute y length. Default value is 0

time_stamp (*double*) the time stamp

quality (*AttrQuality*) the attribute quality factor

Throws *DevFailed* If the attribute data type is not coherent.

push_att_conf_event (*self, attr*) → None

Push an attribute configuration event.

Parameters (*Attribute*) the attribute for which the configuration event will be sent.

Return None

New in PyTango 7.2.1

push_change_event (*self, attr_name*) → None

push_change_event (*self, attr_name, except*) -> None

push_change_event (*self, attr_name, data, dim_x = 1, dim_y = 0*) -> None

push_change_event (*self, attr_name, str_data, data*) -> None

push_change_event (*self, attr_name, data, time_stamp, quality, dim_x = 1, dim_y = 0*) -> None

push_change_event (*self, attr_name, str_data, data, time_stamp, quality*) -> None

Push a change event for the given attribute name. The event is pushed to the notification daemon.

Parameters

attr_name (*str*) attribute name

data the data to be sent as attribute event data. Data must be compatible with the attribute type and format. for SPECTRUM and IMAGE attributes, data can be any type of sequence of elements compatible with the attribute type

str_data (*str*) special variation for DevEncoded data type. In this case 'data' must be a str or an object with the buffer interface.

except (*DevFailed*) Instead of data, you may want to send an exception.

dim_x (*int*) the attribute x length. Default value is 1

dim_y (*int*) the attribute y length. Default value is 0

time_stamp (*double*) the time stamp

quality (*AttrQuality*) the attribute quality factor

Throws *DevFailed* If the attribute data type is not coherent.

push_data_ready_event (*self, attr_name, counter=0*) → *None*

Push a data ready event for the given attribute name. The event is pushed to the notification daemon.

The method needs only the attribute name and an optional "counter" which will be passed unchanged within the event

Parameters

attr_name (*str*) attribute name

counter (*int*) the user counter

Return *None*

Throws *DevFailed* If the attribute name is unknown.

push_event (*self, attr_name, filt_names, filt_vals*) → *None*

push_event (*self, attr_name, filt_names, filt_vals, data, dim_x = 1, dim_y = 0*) → *None*

push_event (*self, attr_name, filt_names, filt_vals, str_data, data*) → *None*

push_event (*self, attr_name, filt_names, filt_vals, data, time_stamp, quality, dim_x = 1, dim_y = 0*) → *None*

push_event (*self, attr_name, filt_names, filt_vals, str_data, data, time_stamp, quality*) → *None*

Push a user event for the given attribute name. The event is pushed to the notification daemon.

Parameters

attr_name (*str*) attribute name

filt_names (*sequence<str>*) the filterable fields name

filt_vals (*sequence<double>*) the filterable fields value

data the data to be sent as attribute event data. Data must be compatible with the attribute type and format. for SPECTRUM and IMAGE attributes, data can be any type of sequence of elements compatible with the attribute type

str_data (*str*) special variation for DevEncoded data type. In this case 'data' must be a str or an object with the buffer interface.

dim_x (*int*) the attribute x length. Default value is 1

dim_y (*int*) the attribute y length. Default value is 0

time_stamp (*double*) the time stamp

quality (*AttrQuality*) the attribute quality factor

Throws *DevFailed* If the attribute data type is not coherent.

push_pipe_event (*self, blob*) → *None*

Push an pipe event.

Parameters the blob which pipe event will be send.

Return *None*

New in PyTango 9.2.2

read_attr_hardware (*self, attr_list*) → *None*

Read the hardware to return attribute value(s). Default method to implement an action necessary on a device to read the hardware involved in a a read attribute CORBA call. This method must be redefined in sub-classes in order to support attribute reading

Parameters

attr_list [(sequence<int>) list of indices in the device object attribute vector] of an attribute to be read.

Return *None*

Throws *DevFailed* This method does not throw exception but a redefined method can.

register_signal (*self, signo*) → *None*

Register a signal. Register this device as device to be informed when signal signo is sent to to the device server process

Parameters

signo (*int*) signal identifier

Return *None*

remove_attribute (*self, attr_name*) → *None*

Remove one attribute from the device attribute list.

Parameters

attr_name (*str*) attribute name

Return *None*

Throws *DevFailed*

remove_command (*self, attr_name*) → *None*

Remove one command from the device command list.

Parameters

cmd_name (*str*) command name to be removed from the list

free_it Boolean set to true if the command object must be freed.

clean_db Clean command related information (included polling info if the command is polled) from database.

Return *None*

Throws *DevFailed*

set_archive_event (*self*, *attr_name*, *implemented*, *detect=True*) → *None*

Set an implemented flag for the attribute to indicate that the server fires archive events manually, without the polling to be started. If the detect parameter is set to true, the criteria specified for the archive event are verified and the event is only pushed if they are fullfilled. If detect is set to false the event is fired without any value checking!

Parameters

attr_name (*str*) attribute name

implemented (*bool*) True when the server fires change events manually.

detect (*bool*) Triggers the verification of the change event properties when set to true. Default value is true.

Return *None*

set_change_event (*self*, *attr_name*, *implemented*, *detect=True*) → *None*

Set an implemented flag for the attribute to indicate that the server fires change events manually, without the polling to be started. If the detect parameter is set to true, the criteria specified for the change event are verified and the event is only pushed if they are fullfilled. If detect is set to false the event is fired without any value checking!

Parameters

attr_name (*str*) attribute name

implemented (*bool*) True when the server fires change events manually.

detect (*bool*) Triggers the verification of the change event properties when set to true. Default value is true.

Return *None*

set_state (*self*, *new_state*) → *None*

Set device state.

Parameters

new_state (*DevState*) the new device state

Return *None*

set_status (*self*, *new_status*) → *None*

Set device status.

Parameters

new_status (*str*) the new device status

Return *None*

signal_handler (*self*, *signo*) → *None*

Signal handler. The method executed when the signal arrived in the device server process. This method is defined as virtual and then, can be redefined following device needs.

Parameters**signo** (`int`) the signal number**Return** None**Throws** *DevFailed* This method does not throw exception but a redefined method can.**stop_polling** (*self*) → None**stop_polling** (*self*, *with_db_upd*) → None

Stop all polling for a device. if the device is polled, call this method before deleting it.

Parameters**with_db_upd** (`bool`) Is it necessary to update db ?**Return** None*New in PyTango 7.1.2***unregister_signal** (*self*, *signo*) → None

Unregister a signal. Unregister this device as device to be informed when signal signo is sent to to the device server process

Parameters**signo** (`int`) signal identifier**Return** None**warn_stream** (*self*, *msg*, **args*) → None

Sends the given message to the tango warn stream.

Since PyTango 7.1.3, the same can be achieved with:

```
print(msg, file=self.log_warn)
```

Parameters**msg** (`str`) the message to be sent to the warn stream**Return** None**write_attr_hardware** (*self*) → None

Write the hardware for attributes. Default method to implement an action necessary on a device to write the hardware involved in a a write attribute. This method must be redefined in sub-classes in order to support writable attribute

Parameters**attr_list** [(sequence<int>) list of indices in the device object attribute vector] of an attribute to be written.**Return** None**Throws** *DevFailed* This method does not throw exception but a redefined method can.

5.3.3 DeviceClass

class `tango.DeviceClass`

Base class for all TANGO device-class class. A TANGO device-class class is a class where is stored all data/method common to all devices of a TANGO device class

DeviceClass.add_wiz_class_prop(`self, str, str`) → `None`

`add_wiz_class_prop` (`self, str, str, str`) → `None`

For internal usage only

Parameters `None`

Return `None`

DeviceClass.add_wiz_dev_prop(`self, str, str`) → `None`

`add_wiz_dev_prop` (`self, str, str, str`) → `None`

For internal usage only

Parameters `None`

Return `None`

create_device (`self, device_name, alias=None, cb=None`) → `None`

Creates a new device of the given class in the database, creates a new DeviceImpl for it and calls `init_device` (just like it is done for existing devices when the DS starts up)

An optional parameter callback is called AFTER the device is registered in the database and BEFORE the `init_device` for the newly created device is called

Throws `tango.DevFailed`:

- the device name exists already or
- the given class is not registered for this DS.
- the cb is not a callable

New in PyTango 7.1.2

Parameters

device_name (`str`) the device name

alias (`str`) optional alias. Default value is `None` meaning do not create device alias

cb (`callable`) a callback that is called AFTER the device is registered in the database and BEFORE the `init_device` for the newly created device is called. Typically you may want to put device and/or attribute properties in the database here. The callback must receive a parameter: device name (`str`). Default value is `None` meaning no callback

Return `None`

delete_device (`self, class_name, device_name`) → `None`

Deletes an existing device from the database and from this running server

Throws `tango.DevFailed`:

- the device name doesn't exist in the database
- the device name doesn't exist in this DS.

New in PyTango 7.1.2

Parameters

class_name (*str*) the device class name

device_name (*str*) the device name

Return None

device_destroyer (*name*)
for internal usage only

device_factory (*device_list*)
for internal usage only

device_name_factory (*self, dev_name_list*) → None

Create device(s) name list (for no database device server). This method can be re-defined in DeviceClass sub-class for device server started without database. Its rule is to initialise class device name. The default method does nothing.

Parameters

dev_name_list (*seq*) sequence of devices to be filled

Return None

dyn_attr (*self, device_list*) → None

Default implementation does not do anything Overwrite in order to provide dynamic attributes

Parameters

device_list (*seq*) sequence of devices of this class

Return None

export_device (*self, dev, corba_dev_name='Unused'*) → None

For internal usage only

Parameters

dev (*DeviceImpl*) device object

corba_dev_name (*str*) CORBA device name. Default value is 'Unused'

Return None

get_cmd_by_name (*self, (str)cmd_name*) → *tango.Command*

Get a reference to a command object.

Parameters

cmd_name (*str*) command name

Return (*tango.Command*) *tango.Command* object

New in PyTango 8.0.0

get_command_list (*self*) → *sequence<tango.Command>*

Gets the list of *tango.Command* objects for this class

Parameters None

Return (sequence<tango.Command>) list of tango.Command objects for this class

New in PyTango 8.0.0

get_cvs_location (*self*) → None

Gets the cvs localtion

Parameters None

Return (str) cvs location

get_cvs_tag (*self*) → str

Gets the cvs tag

Parameters None

Return (str) cvs tag

get_device_list (*self*) → sequence<tango.DeviceImpl>

Gets the list of tango.DeviceImpl objects for this class

Parameters None

Return (sequence<tango.DeviceImpl>) list of tango.DeviceImpl objects for this class

get_doc_url (*self*) → str

Get the TANGO device class documentation URL.

Parameters None

Return (str) the TANGO device type name

get_name (*self*) → str

Get the TANGO device class name.

Parameters None

Return (str) the TANGO device class name.

get_type (*self*) → str

Gets the TANGO device type name.

Parameters None

Return (str) the TANGO device type name

register_signal (*self, signo*) → None

register_signal (*self, signo, own_handler=false*) -> None

Register a signal. Register this class as class to be informed when signal signo is sent to to the device server process. The second version of the method is available only under Linux.

Throws tango.DevFailed:

- if the signal number is out of range
- if the operating system failed to register a signal for the process.

Parameters**signo** (*int*) signal identifier**own_handler** (*bool*) true if you want the device signal handler to be executed in its own handler instead of being executed by the signal thread. If this parameter is set to true, care should be taken on how the handler is written. A default false value is provided**Return** None**set_type** (*self, dev_type*) → None

Set the TANGO device type name.

Parameters**dev_type** (*str*) the new TANGO device type name**Return** None**signal_handler** (*self, signo*) → None

Signal handler.

The method executed when the signal arrived in the device server process. This method is defined as virtual and then, can be redefined following device class needs.

Parameters**signo** (*int*) signal identifier**Return** None**unregister_signal** (*self, signo*) → None

Unregister a signal. Unregister this class as class to be informed when signal signo is sent to to the device server process

Parameters**signo** (*int*) signal identifier**Return** None

5.3.4 Logging decorators

LogIt

class `tango.LogIt` (*show_args=False, show_kwargs=False, show_ret=False*)A class designed to be a decorator of any method of a `tango.DeviceImpl` subclass. The idea is to log the entrance and exit of any decorated method.

Example:

```
class MyDevice(tango.Device_4Impl):

    @tango.LogIt()
    def read_Current(self, attr):
        attr.set_value(self._current, 1)
```

All log messages generated by this class have DEBUG level. If you wish to have different log level messages, you should implement subclasses that log to those levels. See, for example, [tango.InfoIt](#).

The constructor receives three optional arguments:

- `show_args` - shows method arguments in log message (defaults to False)
- `show_kwargs` - shows keyword method arguments in log message (defaults to False)
- `show_ret` - shows return value in log message (defaults to False)

DebugIt

class `tango.DebugIt` (*show_args=False, show_kwargs=False, show_ret=False*)

A class designed to be a decorator of any method of a `tango.DeviceImpl` subclass. The idea is to log the entrance and exit of any decorated method as DEBUG level records.

Example:

```
class MyDevice(tango.Device_4Impl):  
  
    @tango.DebugIt()  
    def read_Current(self, attr):  
        attr.set_value(self._current, 1)
```

All log messages generated by this class have DEBUG level.

The constructor receives three optional arguments:

- `show_args` - shows method arguments in log message (defaults to False)
- `show_kwargs` - shows keyword method arguments in log message (defaults to False)
- `show_ret` - shows return value in log message (defaults to False)

InfoIt

class `tango.InfoIt` (*show_args=False, show_kwargs=False, show_ret=False*)

A class designed to be a decorator of any method of a `tango.DeviceImpl` subclass. The idea is to log the entrance and exit of any decorated method as INFO level records.

Example:

```
class MyDevice(tango.Device_4Impl):  
  
    @tango.InfoIt()  
    def read_Current(self, attr):  
        attr.set_value(self._current, 1)
```

All log messages generated by this class have INFO level.

The constructor receives three optional arguments:

- `show_args` - shows method arguments in log message (defaults to False)
- `show_kwargs` - shows keyword method arguments in log message (defaults to False)
- `show_ret` - shows return value in log message (defaults to False)

WarnIt

class `tango.WarnIt` (*show_args=False, show_kwargs=False, show_ret=False*)

A class designed to be a decorator of any method of a `tango.DeviceImpl` subclass. The idea is to log the entrance and exit of any decorated method as WARN level records.

Example:

```
class MyDevice(tango.Device_4Impl):
    @tango.WarnIt()
    def read_Current(self, attr):
        attr.set_value(self._current, 1)
```

All log messages generated by this class have WARN level.

The constructor receives three optional arguments:

- `show_args` - shows method arguments in log message (defaults to False)
- `show_kwargs` - shows keyword method arguments in log message (defaults to False)
- `show_ret` - shows return value in log message (defaults to False)

ErrorIt

class `tango.ErrorIt` (*show_args=False, show_kwargs=False, show_ret=False*)

A class designed to be a decorator of any method of a `tango.DeviceImpl` subclass. The idea is to log the entrance and exit of any decorated method as ERROR level records.

Example:

```
class MyDevice(tango.Device_4Impl):
    @tango.ErrorIt()
    def read_Current(self, attr):
        attr.set_value(self._current, 1)
```

All log messages generated by this class have ERROR level.

The constructor receives three optional arguments:

- `show_args` - shows method arguments in log message (defaults to False)
- `show_kwargs` - shows keyword method arguments in log message (defaults to False)
- `show_ret` - shows return value in log message (defaults to False)

FatalIt

class `tango.FatalIt` (*show_args=False, show_kwargs=False, show_ret=False*)

A class designed to be a decorator of any method of a `tango.DeviceImpl` subclass. The idea is to log the entrance and exit of any decorated method as FATAL level records.

Example:

```
class MyDevice(tango.Device_4Impl):
    @tango.FatalIt()
    def read_Current(self, attr):
        attr.set_value(self._current, 1)
```

All log messages generated by this class have FATAL level.

The constructor receives three optional arguments:

- `show_args` - shows method arguments in log message (defaults to False)

- `show_kwargs` - shows keyword method arguments in log message (defaults to False)
- `show_ret` - shows return value in log message (defaults to False)

5.3.5 Attribute classes

Attr

class `tango.Attr`

This class represents a Tango writable attribute.

get_assoc (*self*) → `str`

Get the associated name.

Parameters None

Return (`bool`) the associated name

get_cl_name (*self*) → `str`

Returns the class name

Parameters None

Return (`str`) the class name

New in PyTango 7.2.0

get_class_properties (*self*) → `sequence<AttrProperty>`

Get the class level attribute properties

Parameters None

Return (`sequence<AttrProperty>`) the class attribute properties

get_disp_level (*self*) → `DispLevel`

Get the attribute display level

Parameters None

Return (`DispLevel`) the attribute display level

get_format (*self*) → `AttrDataFormat`

Get the attribute format

Parameters None

Return (`AttrDataFormat`) the attribute format

get_memorized (*self*) → `bool`

Determine if the attribute is memorized or not.

Parameters None

Return (`bool`) True if the attribute is memorized

get_memorized_init (*self*) → `bool`

Determine if the attribute is written at startup from the memorized value if it is memorized

Parameters None

Return (`bool`) True if initialized with memorized value or not

get_name (*self*) → `str`

Get the attribute name.

Parameters None

Return (`str`) the attribute name

get_polling_period (*self*) → `int`

Get the polling period (mS)

Parameters None

Return (`int`) the polling period (mS)

get_type (*self*) → `int`

Get the attribute data type

Parameters None

Return (`int`) the attribute data type

get_user_default_properties (*self*) → `sequence<AttrProperty>`

Get the user default attribute properties

Parameters None

Return (`sequence<AttrProperty>`) the user default attribute properties

get_writable (*self*) → `AttrWriteType`

Get the attribute write type

Parameters None

Return (`AttrWriteType`) the attribute write type

is_archive_event (*self*) → `bool`

Check if the archive event is fired manually for this attribute.

Parameters None

Return (`bool`) true if a manual fire archive event is implemented.

is_assoc (*self*) → `bool`

Determine if it is assoc.

Parameters None

Return (`bool`) if it is assoc

is_change_event (*self*) → `bool`

Check if the change event is fired manually for this attribute.

Parameters None

Return (`bool`) true if a manual fire change event is implemented.

is_check_archive_criteria (*self*) → `bool`

Check if the archive event criteria should be checked when firing the event manually.

Parameters None

Return (`bool`) true if a archive event criteria will be checked.

is_check_change_criteria (*self*) → `bool`

Check if the change event criteria should be checked when firing the event manually.

Parameters None

Return (`bool`) true if a change event criteria will be checked.

is_data_ready_event (*self*) → `bool`

Check if the data ready event is fired for this attribute.

Parameters None

Return (`bool`) true if firing data ready event is implemented.

New in PyTango 7.2.0

set_archive_event (*self*) → `None`

Set a flag to indicate that the server fires archive events manually without the polling to be started for the attribute. If the detect parameter is set to true, the criteria specified for the archive event are verified and the event is only pushed if they are fulfilled.

If detect is set to false the event is fired without checking!

Parameters

implemented (`bool`) True when the server fires change events manually.

detect (`bool`) Triggers the verification of the archive event properties when set to true.

Return None

set_change_event (*self, implemented, detect*) → `None`

Set a flag to indicate that the server fires change events manually without the polling to be started for the attribute. If the detect parameter is set to true, the criteria specified for the change event are verified and the event is only pushed if they are fulfilled.

If detect is set to false the event is fired without checking!

Parameters

implemented (`bool`) True when the server fires change events manually.

detect (`bool`) Triggers the verification of the change event properties when set to true.

Return None

set_cl_name (*self, cl*) → `None`

Sets the class name

Parameters

`cl` (`str`) new class name

Return None

New in PyTango 7.2.0

set_class_properties (*self*, *props*) → None

Set the class level attribute properties

Parameters

props (`StdAttrPropertyVector`) new class level attribute properties

Return None

set_data_ready_event (*self*, *implemented*) → None

Set a flag to indicate that the server fires data ready events.

Parameters

implemented (`bool`) True when the server fires data ready events

Return None

New in PyTango 7.2.0

set_default_properties (*self*) → None

Set default attribute properties.

Parameters

attr_prop (`UserDefaultAttrProp`) the user default property class

Return None

set_disp_level (*self*, *disp_level*) → None

Set the attribute display level.

Parameters

disp_level (`DispLevel`) the new display level

Return None

set_memorized (*self*) → None

Set the attribute as memorized in database (only for scalar and writable attribute)
With no argument the setpoint will be written to the attribute during initialisation!

Parameters None

Return None

set_memorized_init (*self*, *write_on_init*) → None

Set the initialisation flag for memorized attributes true = the setpoint value will be written to the attribute on initialisation false = only the attribute setpoint is initialised. No action is taken on the attribute

Parameters

write_on_init (`bool`) if true the setpoint value will be written to the attribute on initialisation

Return None

set_polling_period (`self, period`) → `None`

Set the attribute polling update period.

Parameters

period (`int`) the attribute polling period (in mS)

Return None

Attribute

class `tango.Attribute`

This class represents a Tango attribute.

check_alarm (`self`) → `bool`

Check if the attribute read value is below/above the alarm level.

Parameters None

Return (`bool`) true if the attribute is in alarm condition.

Throws `DevFailed` If no alarm level is defined.

get_assoc_ind (`self`) → `int`

Get index of the associated writable attribute.

Parameters None

Return (`int`) the index in the main attribute vector of the associated writable attribute

get_assoc_name (`self`) → `str`

Get name of the associated writable attribute.

Parameters None

Return (`str`) the associated writable attribute name

get_attr_serial_model (`self`) → `AttrSerialModel`

Get attribute serialization model.

Parameters None

Return (`AttrSerialModel`) The attribute serialization model

New in PyTango 7.1.0

get_data_format (`self`) → `AttrDataFormat`

Get attribute data format.

Parameters None

Return (*AttrDataFormat*) the attribute data format

get_data_size (*self*) → None

Get attribute data size.

Parameters None

Return (*int*) the attribute data size

get_data_type (*self*) → *int*

Get attribute data type.

Parameters None

Return (*int*) the attribute data type

get_date (*self*) → *TimeVal*

Get a COPY of the attribute date.

Parameters None

Return (*TimeVal*) the attribute date

get_label (*self*) → *str*

Get attribute label property.

Parameters None

Return (*str*) the attribute label

get_max_dim_x (*self*) → *int*

Get attribute maximum data size in x dimension.

Parameters None

Return (*int*) the attribute maximum data size in x dimension. Set to 1 for scalar attribute

get_max_dim_y (*self*) → *int*

Get attribute maximum data size in y dimension.

Parameters None

Return (*int*) the attribute maximum data size in y dimension. Set to 0 for scalar attribute

get_name (*self*) → *str*

Get attribute name.

Parameters None

Return (*str*) The attribute name

get_polling_period (*self*) → *int*

Get attribute polling period.

Parameters None

Return (`int`) The attribute polling period in mS. Set to 0 when the attribute is not polled

get_properties (*self*, *attr_cfg=None*) → `AttributeConfig`

Get attribute properties.

Parameters

conf the config object to be filled with the attribute configuration. Default is None meaning the method will create internally a new `AttributeConfig_5` and return it. Can be `AttributeConfig`, `AttributeConfig_2`, `AttributeConfig_3`, `AttributeConfig_5` or `MultiAttrProp`

Return (`AttributeConfig`) the config object filled with attribute configuration information

New in PyTango 7.1.4

get_quality (*self*) → `AttrQuality`

Get a COPY of the attribute data quality.

Parameters None

Return (`AttrQuality`) the attribute data quality

get_writable (*self*) → `AttrWriteType`

Get the attribute writable type (RO/WO/RW).

Parameters None

Return (`AttrWriteType`) The attribute write type.

get_x (*self*) → `int`

Get attribute data size in x dimension.

Parameters None

Return (`int`) the attribute data size in x dimension. Set to 1 for scalar attribute

get_y (*self*) → `int`

Get attribute data size in y dimension.

Parameters None

Return (`int`) the attribute data size in y dimension. Set to 1 for scalar attribute

is_archive_event (*self*) → `bool`

Check if the archive event is fired manually (without polling) for this attribute.

Parameters None

Return (`bool`) True if a manual fire archive event is implemented.

New in PyTango 7.1.0

is_change_event (*self*) → `bool`

Check if the change event is fired manually (without polling) for this attribute.

Parameters None

Return (`bool`) True if a manual fire change event is implemented.

New in PyTango 7.1.0

`is_check_archive_criteria` (*self*) → `bool`

Check if the archive event criteria should be checked when firing the event manually.

Parameters None

Return (`bool`) True if a archive event criteria will be checked.

New in PyTango 7.1.0

`is_check_change_criteria` (*self*) → `bool`

Check if the change event criteria should be checked when firing the event manually.

Parameters None

Return (`bool`) True if a change event criteria will be checked.

New in PyTango 7.1.0

`is_data_ready_event` (*self*) → `bool`

Check if the data ready event is fired manually (without polling) for this attribute.

Parameters None

Return (`bool`) True if a manual fire data ready event is implemented.

New in PyTango 7.2.0

`is_max_alarm` (*self*) → `bool`

Check if the attribute is in maximum alarm condition.

Parameters None

Return (`bool`) true if the attribute is in alarm condition (read value above the max. alarm).

`is_max_warning` (*self*) → `bool`

Check if the attribute is in maximum warning condition.

Parameters None

Return (`bool`) true if the attribute is in warning condition (read value above the max. warning).

`is_min_alarm` (*self*) → `bool`

Check if the attribute is in minimum alarm condition.

Parameters None

Return (`bool`) true if the attribute is in alarm condition (read value below the min. alarm).

`is_min_warning` (*self*) → `bool`

Check if the attribute is in minimum warning condition.

Parameters None

Return (`bool`) true if the attribute is in warning condition (read value below the min. warning).

is_polled (*self*) → `bool`

Check if the attribute is polled.

Parameters None

Return (`bool`) true if the attribute is polled.

is_rds_alarm (*self*) → `bool`

Check if the attribute is in RDS alarm condition.

Parameters None

Return (`bool`) true if the attribute is in RDS condition (Read Different than Set).

is_write_associated (*self*) → `bool`

Check if the attribute has an associated writable attribute.

Parameters None

Return (`bool`) True if there is an associated writable attribute

remove_configuration (*self*) → `None`

Remove the attribute configuration from the database. This method can be used to clean-up all the configuration of an attribute to come back to its default values or the remove all configuration of a dynamic attribute before deleting it.

The method removes all configured attribute properties and removes the attribute from the list of polled attributes.

Parameters None

Return None

New in PyTango 7.1.0

set_archive_event (*self*, *implemented*, *detect=True*) → `None`

Set a flag to indicate that the server fires archive events manually, without the polling to be started for the attribute. If the *detect* parameter is set to true, the criteria specified for the archive event are verified and the event is only pushed if they are fulfilled.

Parameters

implemented (`bool`) True when the server fires archive events manually.

detect (`bool`) (optional, default is True) Triggers the verification of the archive event properties when set to true.

Return None

New in PyTango 7.1.0

set_assoc_ind (*self*, *index*) → `None`

Set index of the associated writable attribute.

Parameters

index (`int`) The new index in the main attribute vector of the associated writable attribute

Return None

set_attr_serial_model (*self*, *ser_model*) → void

Set attribute serialization model. This method allows the user to choose the attribute serialization model.

Parameters

ser_model (`AttrSerialModel`) The new serialisation model. The serialization model must be one of `ATTR_BY_KERNEL`, `ATTR_BY_USER` or `ATTR_NO_SYNC`

Return None

New in PyTango 7.1.0

set_change_event (*self*, *implemented*, *detect=True*) → None

Set a flag to indicate that the server fires change events manually, without the polling to be started for the attribute. If the detect parameter is set to true, the criteria specified for the change event are verified and the event is only pushed if they are fulfilled. If detect is set to false the event is fired without any value checking!

Parameters

implemented (`bool`) True when the server fires change events manually.

detect (`bool`) (optional, default is True) Triggers the verification of the change event properties when set to true.

Return None

New in PyTango 7.1.0

set_data_ready_event (*self*, *implemented*) → None

Set a flag to indicate that the server fires data ready events.

Parameters

implemented (`bool`) True when the server fires data ready events manually.

Return None

New in PyTango 7.2.0

set_date (*self*, *new_date*) → None

Set attribute date.

Parameters

new_date (`TimeVal`) the attribute date

Return None

set_properties (*self, attr_cfg, dev*) → None

Set attribute properties.

This method sets the attribute properties value with the content of the files in the AttributeConfig/ AttributeConfig_3 object

Parameters

conf (AttributeConfig or AttributeConfig_3) the config object.

dev (DeviceImpl) the device (not used, maintained for backward compatibility)

New in PyTango 7.1.4

set_quality (*self, quality, send_event=False*) → None

Set attribute data quality.

Parameters

quality (*AttrQuality*) the new attribute data quality

send_event (*bool*) true if a change event should be sent. Default is false.

Return None

set_value (*self, data, dim_x=1, dim_y=0*) → None <= DEPRECATED

set_value (*self, data*) → None

set_value (*self, str_data, data*) → None

Set internal attribute value. This method stores the attribute read value inside the object. This method also stores the date when it is called and initializes the attribute quality factor.

Parameters

data the data to be set. Data must be compatible with the attribute type and format. In the DEPRECATED form for SPECTRUM and IMAGE attributes, data can be any type of FLAT sequence of elements compatible with the attribute type. In the new form (without *dim_x* or *dim_y*) data should be any sequence for SPECTRUM and a SEQUENCE of equal-length SEQUENCES for IMAGE attributes. The recommended sequence is a C continuous and aligned numpy array, as it can be optimized.

str_data (*str*) special variation for DevEncoded data type. In this case 'data' must be a str or an object with the buffer interface.

dim_x (*int*) [DEPRECATED] the attribute x length. Default value is 1

dim_y (*int*) [DEPRECATED] the attribute y length. Default value is 0

Return None

set_value_date_quality (*self, data, time_stamp, quality, dim_x=1, dim_y=0*) → None <= DEPRECATED

set_value_date_quality (*self, data, time_stamp, quality*) → None

set_value_date_quality (*self*, *str_data*, *data*, *time_stamp*, *quality*) -> None

Set internal attribute value, date and quality factor. This method stores the attribute read value, the date and the attribute quality factor inside the object.

Parameters

data the data to be set. Data must be compatible with the attribute type and format. In the DEPRECATED form for SPECTRUM and IMAGE attributes, data can be any type of FLAT sequence of elements compatible with the attribute type. In the new form (without *dim_x* or *dim_y*) data should be any sequence for SPECTRUM and a SEQUENCE of equal-length SEQUENCES for IMAGE attributes. The recommended sequence is a C continuous and aligned numpy array, as it can be optimized.

str_data (*str*) special variation for DevEncoded data type. In this case 'data' must be a str or an object with the buffer interface.

dim_x (*int*) [DEPRECATED] the attribute x length. Default value is 1

dim_y (*int*) [DEPRECATED] the attribute y length. Default value is 0

time_stamp (*double*) the time stamp

quality (*AttrQuality*) the attribute quality factor

Return None

WAttribute

class tango.WAttribute

This class represents a Tango writable attribute.

get_max_value (*self*) → obj

Get attribute maximum value or throws an exception if the attribute does not have a maximum value.

Parameters None

Return (obj) an object with the python maximum value

get_min_value (*self*) → obj

Get attribute minimum value or throws an exception if the attribute does not have a minimum value.

Parameters None

Return (obj) an object with the python minimum value

get_write_value (*self*, *lst*) → None <= DEPRECATED

get_write_value (*self*, *extract_as=ExtractAs.Numpy*) -> obj

Retrieve the new value for writable attribute.

Parameters

extract_as (`ExtractAs`)

lst [out] (list) a list object that will be filled with the attribute write value (DEPRECATED)

Return (`obj`) the attribute write value.

get_write_value_length (`self`) → `int`

Retrieve the new value length (data number) for writable attribute.

Parameters None

Return (`int`) the new value data length

is_max_value (`self`) → `bool`

Check if the attribute has a maximum value.

Parameters None

Return (`bool`) true if the attribute has a maximum value defined

is_min_value (`self`) → `bool`

Check if the attribute has a minimum value.

Parameters None

Return (`bool`) true if the attribute has a minimum value defined

set_max_value (`self, data`) → `None`

Set attribute maximum value.

Parameters

data the attribute maximum value. python data type must be compatible with the attribute data format and type.

Return None

set_min_value (`self, data`) → `None`

Set attribute minimum value.

Parameters

data the attribute minimum value. python data type must be compatible with the attribute data format and type.

Return None

MultiAttribute

class `tango.MultiAttribute`

There is one instance of this class for each device. This class is mainly an aggregate of `Attribute` or `WAttribute` objects. It eases management of multiple attributes

check_alarm (`self`) → `bool`

check_alarm (`self, attr_name`) → `bool`

check_alarm (`self, ind`) → `bool`

- The 1st version of the method checks alarm on all attribute(s) with an alarm defined.

- The 2nd version of the method checks alarm for one attribute with a given name.
- The 3rd version of the method checks alarm for one attribute from its index in the main attributes vector.

Parameters

attr_name (*str*) attribute name

ind (*int*) the attribute index

Return (*bool*) True if at least one attribute is in alarm condition

Throws *DevFailed* If at least one attribute does not have any alarm level defined

New in PyTango 7.0.0

get_attr_by_ind (*self, ind*) → *Attribute*

Get *Attribute* object from its index. This method returns an *Attribute* object from the index in the main attribute vector.

Parameters

ind (*int*) the attribute index

Return (*Attribute*) the attribute object

get_attr_by_name (*self, attr_name*) → *Attribute*

Get *Attribute* object from its name. This method returns an *Attribute* object with a name passed as parameter. The equality on attribute name is case independant.

Parameters

attr_name (*str*) attribute name

Return (*Attribute*) the attribute object

Throws *DevFailed* If the attribute is not defined.

get_attr_ind_by_name (*self, attr_name*) → *int*

Get Attribute index into the main attribute vector from its name. This method returns the index in the Attribute vector (stored in the *MultiAttribute* object) of an attribute with a given name. The name equality is case independant.

Parameters

attr_name (*str*) attribute name

Return (*int*) the attribute index

Throws *DevFailed* If the attribute is not found in the vector.

New in PyTango 7.0.0

get_attr_nb (*self*) → *int*

Get attribute number.

Parameters None

Return (*int*) the number of attributes

New in PyTango 7.0.0

get_attribute_list (*self*) → seq<Attribute>

Get the list of attribute objects.

Return (*seq*) list of attribute objects

New in PyTango 7.2.1

get_w_attr_by_ind (*self, ind*) → WAttribute

Get a writable attribute object from its index. This method returns an *WAttribute* object from the index in the main attribute vector.

Parameters

ind (*int*) the attribute index

Return (*WAttribute*) the attribute object

get_w_attr_by_name (*self, attr_name*) → WAttribute

Get a writable attribute object from its name. This method returns an *WAttribute* object with a name passed as parameter. The equality on attribute name is case independant.

Parameters

attr_name (*str*) attribute name

Return (*WAttribute*) the attribute object

Throws *DevFailed* If the attribute is not defined.

read_alarm (*self, status*) → None

Add alarm message to device status. This method add alarm message to the string passed as parameter. A message is added for each attribute which is in alarm condition

Parameters

status (*str*) a string (should be the device status)

Return None

New in PyTango 7.0.0

UserDefaultAttrProp

class tango.**UserDefaultAttrProp**

User class to set attribute default properties. This class is used to set attribute default properties. Three levels of attributes properties setting are implemented within Tango. The highest property setting level is the database. Then the user default (set using this *UserDefaultAttrProp* class) and finally a Tango library default value

set_abs_change (*self, def_abs_change*) → None <= DEPRECATED

Set default change event *abs_change* property.

Parameters

def_abs_change (*str*) the user default change event *abs_change* property

Return None

Deprecated since PyTango 8.0. Please use `set_event_abs_change` instead.

set_archive_abs_change (*self*, *def_archive_abs_change*) → None <= DEPRECATED

Set default archive event `abs_change` property.

Parameters

def_archive_abs_change (`str`) the user default archive event `abs_change` property

Return None

Deprecated since PyTango 8.0. Please use `set_archive_event_abs_change` instead.

set_archive_event_abs_change (*self*, *def_archive_abs_change*) → None

Set default archive event `abs_change` property.

Parameters

def_archive_abs_change (`str`) the user default archive event `abs_change` property

Return None

New in PyTango 8.0

set_archive_event_period (*self*, *def_archive_period*) → None

Set default archive event `period` property.

Parameters

def_archive_period (`str`) *t*

Return None

New in PyTango 8.0

set_archive_event_rel_change (*self*, *def_archive_rel_change*) → None

Set default archive event `rel_change` property.

Parameters

def_archive_rel_change (`str`) the user default archive event `rel_change` property

Return None

New in PyTango 8.0

set_archive_period (*self*, *def_archive_period*) → None <= DEPRECATED

Set default archive event `period` property.

Parameters

def_archive_period (`str`) *t*

Return None

Deprecated since PyTango 8.0. Please use `set_archive_event_period` instead.

set_archive_rel_change (*self*, *def_archive_rel_change*) → None <= DEPRECATED

Set default archive event rel_change property.

Parameters

def_archive_rel_change (*str*) the user default archive event rel_change property

Return None

Deprecated since PyTango 8.0. Please use set_archive_event_rel_change instead.

set_delta_t (*self, def_delta_t*) → None

Set default RDS alarm delta_t property.

Parameters

def_delta_t (*str*) the user default RDS alarm delta_t property

Return None

set_delta_val (*self, def_delta_val*) → None

Set default RDS alarm delta_val property.

Parameters

def_delta_val (*str*) the user default RDS alarm delta_val property

Return None

set_description (*self, def_description*) → None

Set default description property.

Parameters

def_description (*str*) the user default description property

Return None

set_display_unit (*self, def_display_unit*) → None

Set default display unit property.

Parameters

def_display_unit (*str*) the user default display unit property

Return None

set_enum_labels (*self, enum_labels*) → None

Set default enumeration labels.

Parameters

enum_labels (*seq*) list of enumeration labels

New in PyTango 9.2.0

set_event_abs_change (*self, def_abs_change*) → None

Set default change event abs_change property.

Parameters

def_abs_change (*str*) the user default change event abs_change property

Return None

New in PyTango 8.0

set_event_period (*self*, *def_period*) → None

Set default periodic event period property.

Parameters

def_period (*str*) the user default periodic event period property

Return None

New in PyTango 8.0

set_event_rel_change (*self*, *def_rel_change*) → None

Set default change event rel_change property.

Parameters

def_rel_change (*str*) the user default change event rel_change property

Return None

New in PyTango 8.0

set_format (*self*, *def_format*) → None

Set default format property.

Parameters

def_format (*str*) the user default format property

Return None

set_label (*self*, *def_label*) → None

Set default label property.

Parameters

def_label (*str*) the user default label property

Return None

set_max_alarm (*self*, *def_max_alarm*) → None

Set default max_alarm property.

Parameters

def_max_alarm (*str*) the user default max_alarm property

Return None

set_max_value (*self*, *def_max_value*) → None

Set default max_value property.

Parameters

def_max_value (*str*) the user default max_value property

Return None

set_max_warning (*self*, *def_max_warning*) → None

Set default max_warning property.

Parameters

def_max_warning (*str*) the user default max_warning property

Return None

set_min_alarm (*self*, *def_min_alarm*) → None

Set default min_alarm property.

Parameters

def_min_alarm (*str*) the user default min_alarm property

Return None

set_min_value (*self*, *def_min_value*) → None

Set default min_value property.

Parameters

def_min_value (*str*) the user default min_value property

Return None

set_min_warning (*self*, *def_min_warning*) → None

Set default min_warning property.

Parameters

def_min_warning (*str*) the user default min_warning property

Return None

set_period (*self*, *def_period*) → None <= DEPRECATED

Set default periodic event period property.

Parameters

def_period (*str*) the user default periodic event period property

Return None

Deprecated since PyTango 8.0. Please use set_event_period instead.

set_rel_change (*self*, *def_rel_change*) → None <= DEPRECATED

Set default change event rel_change property.

Parameters

def_rel_change (*str*) the user default change event rel_change property

Return None

Deprecated since PyTango 8.0. Please use set_event_rel_change instead.

set_standard_unit (*self*, *def_standard_unit*) → None

Set default standard unit property.

Parameters

def_standard_unit (*str*) the user default standard unit property

Return None

set_unit (*self, def_unit*) → None

Set default unit property.

Parameters

def_unit (*str*) te user default unit property

Return None

5.3.6 Util

class tango.Util

This class is a used to store TANGO device server process data and to provide the user with a set of utilities method.

This class is implemented using the singleton design pattern. Therefore a device server process can have only one instance of this class and its constructor is not public. Example:

```
util = tango.Util.instance()
print(util.get_host_name())
```

add_Cpp_TgClass (*device_class_name, tango_device_class_name*)

Register a new C++ tango class.

If there is a shared library file called MotorClass.so which contains a MotorClass class and a _create_MotorClass_class method. Example:

```
util.add_Cpp_TgClass('MotorClass', 'Motor')
```

Note: the parameter 'device_class_name' must match the shared library name.

Deprecated since version 7.1.2: Use *tango.Util.add_class()* instead.

add_TgClass (*klass_device_class, klass_device, device_class_name=None*)

Register a new python tango class. Example:

```
util.add_TgClass(MotorClass, Motor)
util.add_TgClass(MotorClass, Motor, 'Motor') # equivalent to previous line
```

Deprecated since version 7.1.2: Use *tango.Util.add_class()* instead.

add_class (*self, class<DeviceClass>, class<DeviceImpl>, language="python"*) → None

Register a new tango class ('python' or 'c++').

If language is 'python' then args must be the same as *tango.Util.add_TgClass()*. Otherwise, args should be the ones in *tango.Util.add_Cpp_TgClass()*. Example:

```
util.add_class(MotorClass, Motor)
util.add_class('CounterClass', 'Counter', language='c++')
```

New in PyTango 7.1.2

connect_db (*self*) → None

Connect the process to the TANGO database. If the connection to the database failed, a message is displayed on the screen and the process is aborted

Parameters None

Return None

create_device (*self*, *class_name*, *device_name*, *alias=None*, *cb=None*) → None

Creates a new device of the given class in the database, creates a new DeviceImpl for it and calls `init_device` (just like it is done for existing devices when the DS starts up)

An optional parameter callback is called AFTER the device is registered in the database and BEFORE the `init_device` for the newly created device is called

Throws tango.DevFailed:

- the device name exists already or
- the given class is not registered for this DS.
- the cb is not a callable

New in PyTango 7.1.2

Parameters

class_name (*str*) the device class name

device_name (*str*) the device name

alias (*str*) optional alias. Default value is None meaning do not create device alias

cb (*callable*) a callback that is called AFTER the device is registered in the database and BEFORE the `init_device` for the newly created device is called. Typically you may want to put device and/or attribute properties in the database here. The callback must receive a parameter: device name (*str*). Default value is None meaning no callback

Return None

delete_device (*self*, *class_name*, *device_name*) → None

Deletes an existing device from the database and from this running server

Throws tango.DevFailed:

- the device name doesn't exist in the database
- the device name doesn't exist in this DS.

New in PyTango 7.1.2

Parameters

class_name (*str*) the device class name

device_name (*str*) the device name

Return None

get_class_list (*self*) → seq<DeviceClass>

Returns a list of objects of inheriting from DeviceClass

Parameters None

Return (*seq*) a list of objects of inheriting from DeviceClass

get_database (*self*) → Database

Get a reference to the TANGO database object

Parameters None

Return (*Database*) the database

New in PyTango 7.0.0

get_device_by_name (*self, dev_name*) → DeviceImpl

Get a device reference from its name

Parameters

dev_name (*str*) The TANGO device name

Return (*DeviceImpl*) The device reference

New in PyTango 7.0.0

get_device_list (*self*) → sequence<DeviceImpl>

Get device list from name. It is possible to use a wild card (*) in the name parameter (e.g. "*", "/tango/tangotest/n*", ...)

Parameters None

Return (sequence<DeviceImpl>) the list of device objects

New in PyTango 7.0.0

get_device_list_by_class (*self, class_name*) → sequence<DeviceImpl>

Get the list of device references for a given TANGO class. Return the list of references for all devices served by one implementation of the TANGO device pattern implemented in the process.

Parameters

class_name (*str*) The TANGO device class name

Return (sequence<DeviceImpl>) The device reference list

New in PyTango 7.0.0

get_ds_exec_name (*self*) → *str*

Get a COPY of the device server executable name.

Parameters None

Return (*str*) a COPY of the device server executable name.

New in PyTango 3.0.4

get_ds_inst_name (*self*) → *str*

Get a COPY of the device server instance name.

Parameters None

Return (*str*) a COPY of the device server instance name.

New in PyTango 3.0.4

get_ds_name (*self*) → *str*

Get the device server name. The device server name is the <device server executable name>/<the device server instance name>

Parameters None

Return (*str*) device server name

New in PyTango 3.0.4

get_dserver_device (*self*) → *DServer*

Get a reference to the dserver device attached to the device server process

Parameters None

Return (*DServer*) A reference to the dserver device

New in PyTango 7.0.0

get_host_name (*self*) → *str*

Get the host name where the device server process is running.

Parameters None

Return (*str*) the host name where the device server process is running

New in PyTango 3.0.4

get_pid (*self*) → *TangoSys_Pid*

Get the device server process identifier.

Parameters None

Return (*int*) the device server process identifier

get_pid_str (*self*) → *str*

Get the device server process identifier as a string.

Parameters None

Return (*str*) the device server process identifier as a string

New in PyTango 3.0.4

get_polling_threads_pool_size (*self*) → *int*

Get the polling threads pool size.

Parameters None

Return (*int*) the maximum number of threads in the polling threads pool

get_serial_model (*self*) → *SerialModel*

Get the serialization model.

Parameters None

Return (*SerialModel*) the serialization model

get_server_version (*self*) → *str*

Get the device server version.

Parameters None

Return (`str`) the device server version.

`get_sub_dev_diag` (*self*) → `SubDevDiag`

Get the internal sub device manager

Parameters None

Return (`SubDevDiag`) the sub device manager

New in PyTango 7.0.0

`get_tango_lib_release` (*self*) → `int`

Get the TANGO library version number.

Parameters None

Return (`int`) The Tango library release number coded in 3 digits (for instance 550,551,552,600,...)

`get_trace_level` (*self*) → `int`

Get the process trace level.

Parameters None

Return (`int`) the process trace level.

`get_version_str` (*self*) → `str`

Get the IDL TANGO version.

Parameters None

Return (`str`) the IDL TANGO version.

New in PyTango 3.0.4

`is_device_restarting` (*self*, (*str*)*dev_name*) → `bool`

Check if the device is actually restarted by the device server process admin device with its `DevRestart` command

Parameters *dev_name* : (`str`) device name

Return (`bool`) True if the device is restarting.

New in PyTango 8.0.0

`is_svr_shutting_down` (*self*) → `bool`

Check if the device server process is in its shutting down sequence

Parameters None

Return (`bool`) True if the server is in its shutting down phase.

New in PyTango 8.0.0

`is_svr_starting` (*self*) → `bool`

Check if the device server process is in its starting phase

Parameters None

Return (`bool`) True if the server is in its starting phase

New in PyTango 8.0.0

reset_filedatabase (*self*) → `None`

Reread the file database

Parameters None

Return None

New in PyTango 7.0.0

server_init (*self*, *with_window=False*) → `None`

Initialize all the device server pattern(s) embedded in a device server process.

Parameters

with_window (`bool`) default value is False

Return None

Throws *DevFailed* If the device pattern initialistaion failed

server_run (*self*) → `None`

Run the CORBA event loop. This method runs the CORBA event loop. For UNIX or Linux operating system, this method does not return. For Windows in a non-console mode, this method start a thread which enter the CORBA event loop.

Parameters None

Return None

server_set_event_loop (*self*, *event_loop*) → `None`

This method registers an event loop function in a Tango server. This function will be called by the process main thread in an infinite loop The process will not use the classical ORB blocking event loop. It is the user responsibility to code this function in a way that it implements some kind of blocking in order not to load the computer CPU. The following piece of code is an example of how you can use this feature:

```
_LOOP_NB = 1
def looping():
    global _LOOP_NB
    print "looping", _LOOP_NB
    time.sleep(0.1)
    _LOOP_NB += 1
    return _LOOP_NB > 100

def main():
    py = tango.Util(sys.argv)

    # ...

    U = tango.Util.instance()
    U.server_set_event_loop(looping)
    U.server_init()
    U.server_run()
```

Parameters None

Return None

New in PyTango 8.1.0

set_polling_threads_pool_size (*self*, *thread_nb*) → None

Set the polling threads pool size.

Parameters

thread_nb (*int*) the maximum number of threads in the polling threads pool

Return None

New in PyTango 7.0.0

set_serial_model (*self*, *ser*) → None

Set the serialization model.

Parameters

ser (*SerialModel*) the new serialization model. The serialization model must be one of BY_DEVICE, BY_CLASS, BY_PROCESS or NO_SYNC

Return None

set_server_version (*self*, *vers*) → None

Set the device server version.

Parameters

vers (*str*) the device server version

Return None

set_trace_level (*self*, *level*) → None

Set the process trace level.

Parameters

level (*int*) the new process level

Return None

trigger_attr_polling (*self*, *dev*, *name*) → None

Trigger polling for polled attribute. This method send the order to the polling thread to poll one object registered with an update period defined as "externally triggered"

Parameters

dev (*DeviceImpl*) the TANGO device

name (*str*) the attribute name which must be polled

Return None

trigger_cmd_polling (*self*, *dev*, *name*) → None

Trigger polling for polled command. This method send the order to the polling thread to poll one object registered with an update period defined as "externally triggered"

Parameters

dev (`DeviceImpl`) the TANGO device

name (`str`) the command name which must be polled

Return None

Throws `DevFailed` If the call failed

unregister_server (`self`) → None

Unregister a device server process from the TANGO database. If the database call fails, a message is displayed on the screen and the process is aborted

Parameters None

Return None

New in PyTango 7.0.0

5.4 Database API

class `tango.Database`

Database is the high level Tango object which contains the link to the static database. Database provides methods for all database commands : `get_device_property()`, `put_device_property()`, `info()`, etc.. To create a Database, use the default constructor. Example:

```
db = Database()
```

The constructor uses the `TANGO_HOST` env. variable to determine which instance of the Database to connect to.

add_device (`self`, `dev_info`) → None

Add a device to the database. The device name, server and class are specified in the `DbDevInfo` structure

Example

```
dev_info = DbDevInfo()
dev_info.name = 'my/own/device'
dev_info._class = 'MyDevice'
dev_info.server = 'MyServer/test'
db.add_device(dev_info)
```

Parameters

dev_info (`DbDevInfo`) device information

Return None

add_server (`self`, `servername`, `dev_info`, `with_dserver=False`) → None

Add a (group of) devices to the database. This is considered as a low level call because it may render the database inconsistent if it is not used properly.

If `with_dserver` parameter is set to False (default), this call will only register the given `dev_info(s)`. You should include in the list of `dev_info` an entry to the usually hidden **DServer** device.

If `with_dserver` parameter is set to True, the call will add an additional **DServer** device if it is not included in the `dev_info` parameter.

Example using `with_dserver=True`:

```

dev_info1 = DbDevInfo()
dev_info1.name = 'my/own/device'
dev_info1._class = 'MyDevice'
dev_info1.server = 'MyServer/test'
db.add_server(dev_info1.server, dev_info, with_dserver=True)

```

Same example using *with_dserver=False*:

```

dev_info1 = DbDevInfo()
dev_info1.name = 'my/own/device'
dev_info1._class = 'MyDevice'
dev_info1.server = 'MyServer/test'

dev_info2 = DbDevInfo()
dev_info2.name = 'dserver/' + dev_info1.server
dev_info2._class = 'DServer'
dev_info2.server = dev_info1.server

dev_info = dev_info1, dev_info2
db.add_server(dev_info1.server, dev_info)

```

New in version 8.1.7: added *with_dserver* parameter

Parameters

servername (*str*) server name

dev_info (sequence<DbDevInfo> | DbDevInfos | DbDevInfo) containing the server device(s) information

with_dserver (*bool*) whether or not to auto create **DServer** device in server

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (*DB_SQLError*)

build_connection (*self*) → None

Tries to build a connection to the Database server.

Parameters None

Return None

New in PyTango 7.0.0

check_access_control (*self*, *dev_name*) → *AccessControlType*

Check the access for the given device for this client.

Parameters

dev_name (*str*) device name

Return the access control type as a *AccessControlType* object

New in PyTango 7.0.0

check_tango_host (*self*, *tango_host_env*) → None

Check the TANGO_HOST environment variable syntax and extract database server host(s) and port(s) from it.

Parameters

tango_host_env (*str*) The TANGO_HOST env. variable value

Return None

New in PyTango 7.0.0

delete_attribute_alias (*self, alias*) → None

Remove the alias associated to an attribute name.

Parameters

alias (*str*) alias

Return None

Throws *ConnectionFailed, CommunicationFailed, DevFailed* from device (DB_SQLError)

delete_class_attribute_property (*self, class_name, value*) → None

Delete a list of attribute properties for the specified class.

Parameters

class_name (*str*) class name

propnames can be one of the following:

1. DbData [in] - several property data to be deleted
2. sequence<str> [in]- several property data to be deleted
3. sequence<DbDatum> [in] - several property data to be deleted
4. dict<str, seq<str>> keys are attribute names and value being a list of attribute property names

Return None

Throws *ConnectionFailed, CommunicationFailed DevFailed* from device (DB_SQLError)

delete_class_pipe_property (*self, class_name, value*) → None

Delete a list of pipe properties for the specified class.

Parameters

class_name (*str*) class name

propnames can be one of the following:

1. DbData [in] - several property data to be deleted
2. sequence<str> [in]- several property data to be deleted
3. sequence<DbDatum> [in] - several property data to be deleted
4. dict<str, seq<str>> keys are pipe names and value being a list of pipe property names

Return None

Throws *ConnectionFailed, CommunicationFailed DevFailed* from device (DB_SQLError)

delete_class_property (*self, class_name, value*) → None

Delete a the given of properties for the specified class.

Parameters

class_name (`str`) class name

value can be one of the following:

1. `str` [in] - single property data to be deleted
2. `DbDatum` [in] - single property data to be deleted
3. `DbData` [in] - several property data to be deleted
4. `sequence<str>` [in]- several property data to be deleted
5. `sequence<DbDatum>` [in] - several property data to be deleted
6. `dict<str, obj>` [in] - keys are property names to be deleted (values are ignored)
7. `dict<str, DbDatum>` [in] - several `DbDatum.name` are property names to be deleted (keys are ignored)

Return None

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device (`DB_SQLError`)

delete_device (`self, dev_name`) → None

Delete the device of the specified name from the database.

Parameters

dev_name (`str`) device name

Return None

delete_device_alias (`self, alias`) → void

Delete a device alias

Parameters

alias (`str`) alias name

Return None

delete_device_attribute_property (`self, dev_name, value`) → None

Delete a list of attribute properties for the specified device.

Parameters

devname (`string`) device name

propnames can be one of the following: 1. `DbData` [in] - several property data to be deleted 2. `sequence<str>` [in]- several property data to be deleted 3. `sequence<DbDatum>` [in] - several property data to be deleted 3. `dict<str, seq<str>>` keys are attribute names and value being a list of attribute property names

Return None

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device (`DB_SQLError`)

delete_device_pipe_property (*self, dev_name, value*) → *None*

Delete a list of pipe properties for the specified device.

Parameters

devname (*string*) device name

propnames can be one of the following: 1. *DbData* [*in*] - several property data to be deleted 2. *sequence<str>* [*in*]- several property data to be deleted 3. *sequence<DbDatum>* [*in*] - several property data to be deleted 3. *dict<str, seq<str>>* keys are pipe names and value being a list of pipe property names

Return *None*

Throws *ConnectionFailed, CommunicationFailed, DevFailed* from device (*DB_SQLError*)

delete_device_property (*self, dev_name, value*) → *None*

Delete a the given of properties for the specified device.

Parameters

dev_name (*str*) object name

value can be one of the following: 1. *str* [*in*] - single property data to be deleted 2. *DbDatum* [*in*] - single property data to be deleted 3. *DbData* [*in*] - several property data to be deleted 4. *sequence<str>* [*in*]- several property data to be deleted 5. *sequence<DbDatum>* [*in*] - several property data to be deleted 6. *dict<str, obj>* [*in*] - keys are property names to be deleted (values are ignored) 7. *dict<str, DbDatum>* [*in*] - several *DbDatum.name* are property names to be deleted (keys are ignored)

Return *None*

Throws *ConnectionFailed, CommunicationFailed, DevFailed* from device (*DB_SQLError*)

delete_property (*self, obj_name, value*) → *None*

Delete a the given of properties for the specified object.

Parameters

obj_name (*str*) object name

value can be one of the following:

1. *str* [*in*] - single property data to be deleted
2. *DbDatum* [*in*] - single property data to be deleted
3. *DbData* [*in*] - several property data to be deleted
4. *sequence<string>* [*in*]- several property data to be deleted
5. *sequence<DbDatum>* [*in*] - several property data to be deleted
6. *dict<str, obj>* [*in*] - keys are property names to be deleted (values are ignored)
7. *dict<str, DbDatum>* [*in*] - several *DbDatum.name* are property names to be deleted (keys are ignored)

Return *None*

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

delete_server (*self*, *server*) → *None*

Delete the device server and its associated devices from database.

Parameters

server (*str*) name of the server to be deleted with format: <server name>/<instance>

Return *None*

delete_server_info (*self*, *server*) → *None*

Delete server information of the specified server from the database.

Parameters

server (*str*) name of the server to be deleted with format: <server name>/<instance>

Return *None*

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 3.0.4

export_device (*self*, *dev_export*) → *None*

Update the export info for this device in the database.

Example

```
dev_export = DbDevExportInfo()
dev_export.name = 'my/own/device'
dev_export.iior = <the real iior>
dev_export.host = <the host>
dev_export.version = '3.0'
dev_export.pid = '....'
db.export_device(dev_export)
```

Parameters

dev_export (*DbDevExportInfo*) export information

Return *None*

export_event (*self*, *event_data*) → *None*

Export an event to the database.

Parameters

eventdata (sequence<*str*>) event data (same as *DbExportEvent* Database command)

Return *None*

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 7.0.0

export_server (*self*, *dev_info*) → *None*

Export a group of devices to the database.

Parameters

devinfo (sequence<DbDevExportInfo> | DbDevExportInfos | DbDevExportInfo) containing the device(s) to export information

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

get_access_except_errors (*self*) → DevErrorList

Returns a reference to the control access exceptions.

Parameters None

Return DevErrorList

New in PyTango 7.0.0

get_alias (*self*, *alias*) → str

Get the device alias name from its name.

Parameters

alias (str) device name

Return alias

New in PyTango 3.0.4

Deprecated since version 8.1.0: Use *get_alias_from_device()* instead

get_alias_from_attribute (*self*, *attr_name*) → str

Get the attribute alias from the full attribute name.

Parameters

attr_name (str) full attribute name

Return attribute alias

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 8.1.0

get_alias_from_device (*self*, *alias*) → str

Get the device alias name from its name.

Parameters

alias (str) device name

Return alias

New in PyTango 8.1.0

get_attribute_alias (*self*, *alias*) → str

Get the full attribute name from an alias.

Parameters

alias (*str*) attribute alias

Return full attribute name

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

Deprecated since version 8.1.0: Use `:class:`Database().get_attribute_from_alias`` instead

get_attribute_alias_list (*self*, *filter*) → DbDatum

Get attribute alias list. The parameter alias is a string to filter the alias list returned. Wildcard (*) is supported. For instance, if the string alias passed as the method parameter is initialised with only the * character, all the defined attribute alias will be returned. If there is no alias with the given filter, the returned array will have a 0 size.

Parameters

filter (*str*) attribute alias filter

Return DbDatum containing the list of matching attribute alias

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

get_attribute_from_alias (*self*, *alias*) → *str*

Get the full attribute name from an alias.

Parameters

alias (*str*) attribute alias

Return full attribute name

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 8.1.0

get_class_attribute_list (*self*, *class_name*, *wildcard*) → DbDatum

Query the database for a list of attributes defined for the specified class which match the specified wildcard.

Parameters

class_name (*str*) class name

wildcard (*str*) attribute name

Return DbDatum containing the list of matching attributes for the given class

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 7.0.0

get_class_attribute_property (*self*, *class_name*, *value*) → dict<str, dict<str, seq<str>>

Query the database for a list of class attribute properties for the specified class. The method returns all the properties for the specified attributes.

Parameters

class_name (*str*) class name

propnames can be one of the following:

1. *str* [*in*] - single attribute properties to be fetched
2. *DbDatum* [*in*] - single attribute properties to be fetched
3. *DbData* [*in,out*] - several attribute properties to be fetched In this case (direct C++ API) the *DbData* will be filled with the property values
4. *sequence<str>* [*in*] - several attribute properties to be fetched
5. *sequence<DbDatum>* [*in*] - several attribute properties to be fetched
6. *dict<str, obj>* [*in,out*] - keys are attribute names In this case the given *dict* values will be changed to contain the several attribute property values

Return a dictionary which keys are the attribute names the value associated with each key being a another dictionary where keys are property names and value is a sequence of strings being the property value.

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (*DB_SQLError*)

get_class_attribute_property_history (*self*, *dev_name*, *attr_name*, *prop_name*) → *DbHistoryList*

Get the list of the last 10 modifications of the specifed class attribute property. Note that *prop_name* and *attr_name* can contain a wildcard character (eg: 'prop*').

Parameters

dev_name (*str*) device name

attr_name (*str*) attribute name

prop_name (*str*) property name

Return *DbHistoryList* containing the list of modifications

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (*DB_SQLError*)

New in PyTango 7.0.0

get_class_for_device (*self*, *dev_name*) → *str*

Return the class of the specified device.

Parameters

dev_name (*str*) device name

Return a string containing the device class

get_class_inheritance_for_device (*self*, *dev_name*) → *DbDatum*

Return the class inheritance scheme of the specified device.

Parameters

devn_ame (*str*) device name

Return *DbDatum* with the inheritance class list

New in PyTango 7.0.0

get_class_list (*self, wildcard*) → DbDatum

Query the database for a list of classes which match the specified wildcard

Parameters

wildcard (*str*) class wildcard

Return DbDatum containing the list of matching classes

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 7.0.0

get_class_pipe_list (*self, class_name, wildcard*) → DbDatum

Query the database for a list of pipes defined for the specified class which match the specified wildcard. This corresponds to the pure C++ API call.

Parameters

class_name (*str*) class name

wildcard (*str*) pipe name

Return DbDatum containing the list of matching pipes for the given class

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

get_class_pipe_property (*self, class_name, value*) → dict<str, dict<str, seq<str>>

Query the database for a list of class pipe properties for the specified class. The method returns all the properties for the specified pipes.

Parameters

class_name (*str*) class name

propnames can be one of the following:

1. str [in] - single pipe properties to be fetched
2. DbDatum [in] - single pipe properties to be fetched
3. DbData [in,out] - several pipe properties to be fetched In this case (direct C++ API) the DbData will be filled with the property values
4. sequence<str> [in] - several pipe properties to be fetched
5. sequence<DbDatum> [in] - several pipe properties to be fetched
6. dict<str, obj> [in,out] - keys are pipe names In this case the given dict values will be changed to contain the several pipe property values

Return a dictionary which keys are the pipe names the value associated with each key being a another dictionary where keys are property names and value is a sequence of strings being the property value.

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

get_class_pipe_property_history (*self, dev_name, pipe_name, prop_name*) → DbHistoryList

Get the list of the last 10 modifications of the specified class pipe property. Note that *prop_name* and *attr_name* can contain a wildcard character (eg: 'prop*').

Parameters

dev_name (*str*) device name

pipe_name (*str*) pipe name

prop_name (*str*) property name

Return DbHistoryList containing the list of modifications

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

get_class_property (*self, class_name, value*) → dict<str, seq<str>>

Query the database for a list of class properties.

Parameters

class_name (*str*) class name

value can be one of the following:

1. *str* [in] - single property data to be fetched
2. *tango.DbDatum* [in] - single property data to be fetched
3. *tango.DbData* [in,out] - several property data to be fetched
In this case (direct C++ API) the *DbData* will be filled with the property values
4. *sequence<str>* [in] - several property data to be fetched
5. *sequence<DbDatum>* [in] - several property data to be fetched
6. *dict<str, obj>* [in,out] - keys are property names In this case the given dict values will be changed to contain the several property values

Return a dictionary which keys are the property names the value associated with each key being a sequence of strings being the property value.

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

get_class_property_history (*self, class_name, prop_name*) → DbHistoryList

Get the list of the last 10 modifications of the specified class property. Note that *propname* can contain a wildcard character (eg: 'prop*').

Parameters

class_name (*str*) class name

prop_name (*str*) property name

Return DbHistoryList containing the list of modifications

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 7.0.0

get_class_property_list (*self*, *class_name*) → DbDatum

Query the database for a list of properties defined for the specified class.

Parameters

class_name (*str*) class name

Return DbDatum containing the list of properties for the specified class

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

get_device_alias (*self*, *alias*) → *str*

Get the device name from an alias.

Parameters

alias (*str*) alias

Return device name

Deprecated since version 8.1.0: Use *get_device_from_alias()* instead

get_device_alias_list (*self*, *filter*) → DbDatum

Get device alias list. The parameter alias is a string to filter the alias list returned. Wildcard (*) is supported.

Parameters

filter (*str*) a string with the alias filter (wildcard (*) is supported)

Return DbDatum with the list of device names

New in PyTango 7.0.0

get_device_attribute_list (*self*, *dev_name*, *att_list*) → *None*

Get the list of attribute(s) with some data defined in database for a specified device. Note that this is not the list of all device attributes because not all attribute(s) have some data in database This corresponds to the pure C++ API call.

Parameters

dev_name (*str*) device name

att_list [out] (*StdStringVector*) array that will contain the attribute name list

Return *None*

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

get_device_attribute_property (*self*, *dev_name*, *value*) → *dict<str, dict<str, seq<str>>>*

Query the database for a list of device attribute properties for the specified device. The method returns all the properties for the specified attributes.

Parameters

dev_name (*string*) device name

value can be one of the following:

1. *str [in]* - single attribute properties to be fetched

2. DbDatum [in] - single attribute properties to be fetched
3. DbData [in,out] - several attribute properties to be fetched In this case (direct C++ API) the DbData will be filled with the property values
4. sequence<str> [in] - several attribute properties to be fetched
5. sequence<DbDatum> [in] - several attribute properties to be fetched
6. dict<str, obj> [in,out] - keys are attribute names In this case the given dict values will be changed to contain the several attribute property values

Return a dictionary which keys are the attribute names the value associated with each key being a another dictionary where keys are property names and value is a DbDatum containing the property value.

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

get_device_attribute_property_history (*self*, *dev_name*, *attr_name*, *prop_name*) → DbHistoryList

Get the list of the last 10 modifications of the specified device attribute property. Note that proptime and devname can contain a wildcard character (eg: 'prop*').

Parameters

dev_name (*str*) device name

attr_name (*str*) attribute name

prop_name (*str*) property name

Return DbHistoryList containing the list of modifications

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 7.0.0

get_device_class_list (*self*, *server*) → DbDatum

Query the database for a list of devices and classes served by the specified server. Return a list with the following structure: [device name, class name, device name, class name, ...]

Parameters

server (*str*) name of the server with format: <server name>/<instance>

Return DbDatum containing list with the following structure: [device_name, class name]

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 3.0.4

get_device_domain (*self*, *wildcard*) → DbDatum

Query the database for a list of device domain names which match the wildcard provided (* is wildcard for any character(s)). Domain names are case insensitive.

Parameters**wildcard** (`str`) domain filter**Return** DbDatum with the list of device domain names**get_device_exported** (`self, filter`) → DbDatum

Query the database for a list of exported devices whose names satisfy the supplied filter (* is wildcard for any character(s))

Parameters**filter** (`str`) device name filter (wildcard)**Return** DbDatum with the list of exported devices**get_device_exported_for_class** (`self, class_name`) → DbDatum

Query database for list of exported devices for the specified class.

Parameters**class_name** (`str`) class name**Return** DbDatum with the list of exported devices for the*New in PyTango 7.0.0***get_device_family** (`self, wildcard`) → DbDatum

Query the database for a list of device family names which match the wildcard provided (* is wildcard for any character(s)). Family names are case insensitive.

Parameters**wildcard** (`str`) family filter**Return** DbDatum with the list of device family names**get_device_from_alias** (`self, alias`) → `str`

Get the device name from an alias.

Parameters**alias** (`str`) alias**Return** device name*New in PyTango 8.1.0***get_device_info** (`self, dev_name`) → DbDevFullInfo

Query the database for the full info of the specified device.

Example

```

dev_info = db.get_device_info('my/own/device')
print(dev_info.name)
print(dev_info.class_name)
print(dev_info.ds_full_name)
print(dev_info.exported)
print(dev_info.iior)
print(dev_info.version)
print(dev_info.pid)
print(dev_info.started_date)
print(dev_info.stopped_date)

```

Parameters**dev_name** (*str*) device name**Return** DbDevFullInfo*New in PyTango 8.1.0***get_device_member** (*self, wildcard*) → DbDatum

Query the database for a list of device member names which match the wildcard provided (* is wildcard for any character(s)). Member names are case insensitive.

Parameters**wildcard** (*str*) member filter**Return** DbDatum with the list of device member names**get_device_name** (*self, serv_name, class_name*) → DbDatum

Query the database for a list of devices served by a server for a given device class

Parameters**serv_name** (*str*) server name**class_name** (*str*) device class name**Return** DbDatum with the list of device names**get_device_pipe_list** (*self, dev_name, pipe_list*) → None

Get the list of pipe(s) with some data defined in database for a specified device. Note that this is not the list of all device pipes because not all pipe(s) have some data in database This corresponds to the pure C++ API call.

Parameters**dev_name** (*str*) device name**pipe_list [out]** (*StdStringVector*) array that will contain the pipe name list**Return** None**Throws** *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (*DB_SQLError*)**get_device_pipe_property** (*self, dev_name, value*) → dict<str, dict<str, seq<str>>>

Query the database for a list of device pipe properties for the specified device. The method returns all the properties for the specified pipes.

Parameters**dev_name** (*string*) device name**value** can be one of the following:

1. str [in] - single pipe properties to be fetched
2. DbDatum [in] - single pipe properties to be fetched
3. DbData [in,out] - several pipe properties to be fetched In this case (direct C++ API) the DbData will be filled with the property values

4. sequence<str> [in] - several pipe properties to be fetched
5. sequence<DbDatum> [in] - several pipe properties to be fetched
6. dict<str, obj> [in,out] - keys are pipe names In this case the given dict values will be changed to contain the several pipe property values

Return a dictionary which keys are the pipe names the value associated with each key being a another dictionary where keys are property names and value is a DbDatum containing the property value.

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

get_device_pipe_property_history (*self*, *dev_name*, *pipe_name*, *prop_name*) → DbHistoryList

Get the list of the last 10 modifications of the specified device pipe property. Note that proptime and devname can contain a wildcard character (eg: 'prop*').

Parameters

dev_name (*str*) device name

pipe_name (*str*) pipe name

prop_name (*str*) property name

Return DbHistoryList containing the list of modifications

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

get_device_property (*self*, *dev_name*, *value*) → dict<str, seq<str>>

Query the database for a list of device properties.

Parameters

dev_name (*str*) object name

value can be one of the following:

1. str [in] - single property data to be fetched
2. DbDatum [in] - single property data to be fetched
3. DbData [in,out] - several property data to be fetched In this case (direct C++ API) the DbData will be filled with the property values
4. sequence<str> [in] - several property data to be fetched
5. sequence<DbDatum> [in] - several property data to be fetched
6. dict<str, obj> [in,out] - keys are property names In this case the given dict values will be changed to contain the several property values

Return a dictionary which keys are the property names the value associated with each key being a a sequence of strings being the property value.

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

get_device_property_history (*self*, *dev_name*, *prop_name*) → DbHistoryList

Get the list of the last 10 modifications of the specified device property. Note that `propname` can contain a wildcard character (eg: `'prop*'`). This corresponds to the pure C++ API call.

Parameters

serv_name (`str`) server name

prop_name (`str`) property name

Return `DbHistoryList` containing the list of modifications

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device (`DB_SQLError`)

New in PyTango 7.0.0

get_device_property_list (`self`, `dev_name`, `wildcard`, `array=None`) → `DbData`

Query the database for a list of properties defined for the specified device and which match the specified wildcard. If `array` parameter is given, it must be an object implementing the `'append'` method. If given, it is filled with the matching property names. If not given the method returns a new `DbDatum` containing the matching property names.

New in PyTango 7.0.0

Parameters

dev_name (`str`) device name

wildcard (`str`) property name wildcard

array [out] (sequence) (optional) array that will contain the matching property names.

Return if `container` is `None`, return is a new `DbDatum` containing the matching property names. Otherwise returns the given array filled with the property names

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device

get_device_service_list (`self`, `dev_name`) → `DbDatum`

Query database for the list of services provided by the given device.

Parameters

dev_name (`str`) device name

Return `DbDatum` with the list of services

New in PyTango 8.1.0

get_file_name (`self`) → `str`

Returns the database file name or throws an exception if not using a file database

Parameters None

Return a string containing the database file name

Throws `DevFailed`

New in PyTango 7.2.0

get_host_list (`self`) → `DbDatum`

get_host_list (`self`, `wildcard`) → `DbDatum`

Returns the list of all host names registered in the database.

Parameters

wildcard (*str*) (optional) wildcard (eg: 'l-c0*')

Return DbDatum with the list of registered host names

get_host_server_list (*self, host_name*) → DbDatum

Query the database for a list of servers registered on the specified host.

Parameters

host_name (*str*) host name

Return DbDatum containing list of servers for the specified host

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 3.0.4

get_info (*self*) → *str*

Query the database for some general info about the tables.

Parameters None

Return a multiline string

get_instance_name_list (*self, serv_name*) → DbDatum

Return the list of all instance names existing in the database for the specified server.

Parameters

serv_name (*str*) server name with format <server name>

Return DbDatum containing list of instance names for the specified server

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 3.0.4

get_object_list (*self, wildcard*) → DbDatum

Query the database for a list of object (free properties) for which properties are defined and which match the specified wildcard.

Parameters

wildcard (*str*) object wildcard

Return DbDatum containing the list of object names matching the given wildcard

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 7.0.0

get_object_property_list (*self, obj_name, wildcard*) → DbDatum

Query the database for a list of properties defined for the specified object and which match the specified wildcard.

Parameters

obj_name (*str*) object name

wildcard (*str*) property name wildcard

Return DbDatum with list of properties defined for the specified object and which match the specified wildcard

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 7.0.0

get_property (*self*, *obj_name*, *value*) → dict<str, seq<str>>

Query the database for a list of object (i.e non-device) properties.

Parameters

obj_name (*str*) object name

value can be one of the following:

1. str [in] - single property data to be fetched
2. DbDatum [in] - single property data to be fetched
3. DbData [in,out] - several property data to be fetched In this case (direct C++ API) the DbData will be filled with the property values
4. sequence<str> [in] - several property data to be fetched
5. sequence<DbDatum> [in] - several property data to be fetched
6. dict<str, obj> [in,out] - keys are property names In this case the given dict values will be changed to contain the several property values

Return a dictionary which keys are the property names the value associated with each key being a a sequence of strings being the property value.

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

get_property_forced (*obj_name*, *value*)

get_property(self, obj_name, value) -> dict<str, seq<str>>

Query the database for a list of object (i.e non-device) properties.

Parameters

obj_name (*str*) object name

value can be one of the following:

1. str [in] - single property data to be fetched
2. DbDatum [in] - single property data to be fetched
3. DbData [in,out] - several property data to be fetched In this case (direct C++ API) the DbData will be filled with the property values
4. sequence<str> [in] - several property data to be fetched

5. `sequence<DbDatum> [in]` - several property data to be fetched
6. `dict<str, obj> [in,out]` - keys are property names In this case the given dict values will be changed to contain the several property values

Return a dictionary which keys are the property names the value associated with each key being a a sequence of strings being the property value.

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device (DB_SQLError)

get_property_history (*self*, *obj_name*, *prop_name*) → DbHistoryList

Get the list of the last 10 modifications of the specified object property. Note that propname can contain a wildcard character (eg: 'prop*')

Parameters

serv_name (`str`) server name

prop_name (`str`) property name

Return DbHistoryList containing the list of modifications

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device (DB_SQLError)

New in PyTango 7.0.0

get_server_class_list (*self*, *server*) → DbDatum

Query the database for a list of classes instantiated by the specified server. The DServer class exists in all TANGO servers and for this reason this class is removed from the returned list.

Parameters

server (`str`) name of the server to be deleted with format: <server name>/<instance>

Return DbDatum containing list of class names instantiated by the specified server

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device (DB_SQLError)

New in PyTango 3.0.4

get_server_info (*self*, *server*) → DbServerInfo

Query the database for server information.

Parameters

server (`str`) name of the server to be unexported with format: <server name>/<instance>

Return DbServerInfo with server information

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device (DB_SQLError)

New in PyTango 3.0.4

get_server_list (*self*) → DbDatum
get_server_list (*self*, *wildcard*) → DbDatum

Return the list of all servers registered in the database. If wildcard parameter is given, then the list of matching servers will be returned (ex: Serial/*)

Parameters

wildcard (*str*) host wildcard (ex: Serial/*)

Return DbDatum containing list of registered servers

get_server_name_list (*self*) → DbDatum

Return the list of all server names registered in the database.

Parameters None

Return DbDatum containing list of server names

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 3.0.4

get_services (*self*, *serv_name*, *inst_name*) → DbDatum

Query database for specified services.

Parameters

serv_name (*str*) service name

inst_name (*str*) instance name (can be a wildcard character ("*"))

Return DbDatum with the list of available services

New in PyTango 3.0.4

import_device (*self*, *dev_name*) → DbDevImportInfo

Query the database for the export info of the specified device.

Example

```
dev_imp_info = db.import_device('my/own/device')
print(dev_imp_info.name)
print(dev_imp_info.exported)
print(dev_imp_info.iOr)
print(dev_imp_info.version)
```

Parameters

dev_name (*str*) device name

Return DbDevImportInfo

is_control_access_checked (*self*) → bool

Returns True if control access is checked or False otherwise.

Parameters None

Return (bool) True if control access is checked or False

New in PyTango 7.0.0

is_multi_tango_host (*self*) → bool

Returns if in multi tango host.

Parameters None

Return True if multi tango host or False otherwise

New in PyTango 7.1.4

put_attribute_alias (*self*, *attr_name*, *alias*) → None

Set an alias for an attribute name. The attribute alias is specified by *alias* and the attribute name is specified by *attr_name*. If the given alias already exists, a `DevFailed` exception is thrown.

Parameters

attr_name (`str`) full attribute name

alias (`str`) alias

Return None

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device (`DB_SQLError`)

put_class_attribute_property (*self*, *class_name*, *value*) → None

Insert or update a list of properties for the specified class.

Parameters

class_name (`str`) class name

propdata can be one of the following:

1. `tango.DbData` - several property data to be inserted
2. `sequence<DbDatum>` - several property data to be inserted
3. `dict<str, dict<str, obj>>` keys are attribute names and value being another dictionary which keys are the attribute property names and the value associated with each key being:
 - 3.1 `seq<str>`
 - 3.2 `tango.DbDatum`

Return None

Throws `ConnectionFailed`, `CommunicationFailed`, `DevFailed` from device (`DB_SQLError`)

put_class_pipe_property (*self*, *class_name*, *value*) → None

Insert or update a list of properties for the specified class.

Parameters

class_name (`str`) class name

propdata can be one of the following:

1. `tango.DbData` - several property data to be inserted
2. `sequence<DbDatum>` - several property data to be inserted
3. `dict<str, dict<str, obj>>` keys are pipe names and value being another dictionary which keys are the pipe property names and the value associated with each key being:
 - 3.1 `seq<str>`
 - 3.2 `tango.DbDatum`

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

put_class_property (*self*, *class_name*, *value*) → None

Insert or update a list of properties for the specified class.

Parameters

class_name (*str*) class name

value can be one of the following: 1. DbDatum - single property data to be inserted 2. DbData - several property data to be inserted 3. sequence<DbDatum> - several property data to be inserted 4. dict<str, DbDatum> - keys are property names and value has data to be inserted 5. dict<str, obj> - keys are property names and str(obj) is property value 6. dict<str, seq<str>> - keys are property names and value has data to be inserted

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

put_device_alias (*self*, *dev_name*, *alias*) → None

Query database for list of exported devices for the specified class.

Parameters

dev_name (*str*) device name

alias (*str*) alias name

Return None

put_device_attribute_property (*self*, *dev_name*, *value*) → None

Insert or update a list of properties for the specified device.

Parameters

dev_name (*str*) device name

value can be one of the following:

1. DbData - several property data to be inserted
2. sequence<DbDatum> - several property data to be inserted
3. dict<str, dict<str, obj>> keys are attribute names and value being another dictionary which keys are the attribute property names and the value associated with each key being:
 - 3.1 seq<str>
 - 3.2 tango.DbDatum

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

put_device_pipe_property (*self*, *dev_name*, *value*) → None

Insert or update a list of properties for the specified device.

Parameters

dev_name (*str*) device name

value can be one of the following:

1. DbData - several property data to be inserted
2. sequence<DbDatum> - several property data to be inserted
3. dict<str, dict<str, obj>> keys are pipe names and value being another dictionary which keys are the pipe property names and the value associated with each key being:
 - 3.1 seq<str>
 - 3.2 tango.DbDatum

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

put_device_property (*self*, *dev_name*, *value*) → None

Insert or update a list of properties for the specified device.

Parameters

dev_name (*str*) object name

value can be one of the following:

1. DbDatum - single property data to be inserted
2. DbData - several property data to be inserted
3. sequence<DbDatum> - several property data to be inserted
4. dict<str, DbDatum> - keys are property names and value has data to be inserted
5. dict<str, obj> - keys are property names and str(obj) is property value
6. dict<str, seq<str>> - keys are property names and value has data to be inserted

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

put_property (*self*, *obj_name*, *value*) → None

Insert or update a list of properties for the specified object.

Parameters

obj_name (*str*) object name

value can be one of the following:

1. DbDatum - single property data to be inserted
2. DbData - several property data to be inserted
3. sequence<DbDatum> - several property data to be inserted
4. dict<str, DbDatum> - keys are property names and value has data to be inserted
5. dict<str, obj> - keys are property names and str(obj) is property value
6. dict<str, seq<str>> - keys are property names and value has data to be inserted

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

put_server_info (*self*, *info*) → None

Add/update server information in the database.

Parameters

info (*DbServerInfo*) new server information

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 3.0.4

register_service (*self*, *serv_name*, *inst_name*, *dev_name*) → None

Register the specified service within the database.

Parameters

serv_name (*str*) service name

inst_name (*str*) instance name

dev_name (*str*) device name

Return None

New in PyTango 3.0.4

rename_server (*self*, *old_ds_name*, *new_ds_name*) → None

Rename a device server process.

Parameters

old_ds_name (*str*) old name

new_ds_name (*str*) new name

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 8.1.0

reread_filedatabase (*self*) → None

Force a complete refresh over the database if using a file based database.

Parameters None

Return None

New in PyTango 7.0.0

set_access_checked (*self*, *val*) → None

Sets or unsets the control access check.

Parameters

val (*bool*) True to set or False to unset the access control

Return None

New in PyTango 7.0.0

unexport_device (*self*, *dev_name*) → None

Mark the specified device as unexported in the database

Example

```
db.unexport_device('my/own/device')
```

Parameters

dev_name (*str*) device name

Return None

unexport_event (*self*, *event*) → None

Un-export an event from the database.

Parameters

event (*str*) event

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

New in PyTango 7.0.0

unexport_server (*self*, *server*) → None

Mark all devices exported for this server as unexported.

Parameters

server (*str*) name of the server to be unexported with format:
<server name>/<instance>

Return None

Throws *ConnectionFailed*, *CommunicationFailed*, *DevFailed* from device (DB_SQLError)

unregister_service (*self*, *serv_name*, *inst_name*) → None

Unregister the specified service from the database.

Parameters

serv_name (*str*) service name

inst_name (*str*) instance name

Return None

New in PyTango 3.0.4

write_filedatabase (*self*) → None

Force a write to the file if using a file based database.

Parameters None

Return None

New in PyTango 7.0.0

class `tango.DbDatum`

A single database value which has a name, type, address and value and methods for inserting and extracting C++ native types. This is the fundamental type for specifying database properties. Every property has a name and has one or more values associated with it. A status flag indicates if there is data in the DbDatum object or not. An additional flag allows the user to activate exceptions.

Note: DbDatum is extended to support the python sequence API. This way the DbDatum behaves like a sequence of strings. This allows the user to work with a DbDatum as if it was working with the old list of strings.

New in PyTango 7.0.0

is_empty (*self*) → `bool`

Returns True or False depending on whether the DbDatum object contains data or not. It can be used to test whether a property is defined in the database or not.

Parameters None

Return (`bool`) True if no data or False otherwise.

New in PyTango 7.0.0

size (*self*) → `int`

Returns the number of separate elements in the value.

Parameters None

Return the number of separate elements in the value.

New in PyTango 7.0.0

class `tango.DbDevExportInfo`

A structure containing export info for a device (should be retrieved from the database) with the following members:

- `name` : (`str`) device name
- `ior` : (`str`) CORBA reference of the device
- `host` : name of the computer hosting the server
- `version` : (`str`) version
- `pid` : process identifier

class `tango.DbDevExportInfo`

A structure containing export info for a device (should be retrieved from the database) with the following members:

- `name` : (`str`) device name
- `ior` : (`str`) CORBA reference of the device
- `host` : name of the computer hosting the server
- `version` : (`str`) version
- `pid` : process identifier

class `tango.DbDevImportInfo`

A structure containing import info for a device (should be retrieved from the database) with the following members:

- `name` : (`str`) device name
- `exported` : 1 if device is running, 0 else
- `ior` : (`str`)CORBA reference of the device
- `version` : (`str`) version

class `tango.DbDevInfo`

A structure containing available information for a device with the following members:

- `name` : (`str`) name
- `_class` : (`str`) device class

- `server : (str) server`

class `tango.DbHistory`

A structure containing the modifications of a property. No public members.

get_attribute_name (*self*) → `str`

Returns the attribute name (empty for object properties or device properties)

Parameters None

Return (`str`) attribute name

get_date (*self*) → `str`

Returns the update date

Parameters None

Return (`str`) update date

get_name (*self*) → `str`

Returns the property name.

Parameters None

Return (`str`) property name

get_value (*self*) → `DbDatum`

Returns a COPY of the property value

Parameters None

Return (`DbDatum`) a COPY of the property value

is_deleted (*self*) → `bool`

Returns True if the property has been deleted or False otherwise

Parameters None

Return (`bool`) True if the property has been deleted or False otherwise

class `tango.DbServerInfo`

A structure containing available information for a device server with the following members:

- `name : (str) name`
- `host : (str) host`
- `mode : (str) mode`
- `level : (str) level`

5.5 Encoded API

This feature is only possible since PyTango 7.1.4

class `tango.EncodedAttribute`

decode_gray16 (*da*, *extract_as*=<ExtensionMock name='_tango.ExtractAs.Numpy'
id='140349536893440'>)

Decode a 16 bits grayscale image (GRAY16) and returns a 16 bits gray scale image.

param da `DeviceAttribute` that contains the image

type da *DeviceAttribute*
param extract_as defaults to `ExtractAs.Numpy`
type extract_as *ExtractAs*
return the decoded data

- In case String string is chosen as extract method, a tuple is returned:
width<int>, height<int>, buffer<str>
- In case Numpy is chosen as extract method, a `numpy.ndarray` is returned with `ndim=2`, `shape=(height, width)` and `dtype=numpy.uint16`.
- In case Tuple or List are chosen, a tuple<tuple<int>> or list<list<int>> is returned.

Warning: The PyTango calls that return a *DeviceAttribute* (like *DeviceProxy.read_attribute()* or *DeviceProxy.command_inout()*) automatically extract the contents by default. This method requires that the given *DeviceAttribute* is obtained from a call which **DOESN'T** extract the contents. Example:

```
dev = tango.DeviceProxy("a/b/c")
da = dev.read_attribute("my_attr", extract_as=tango.ExtractAs.Nothing)
enc = tango.EncodedAttribute()
data = enc.decode_gray16(da)
```

decode_gray8 (*da*, *extract_as*=<*ExtensionMock* *name*='tango.ExtractAs.Numpy'
id='140349536893440'>)

Decode a 8 bits grayscale image (JPEG_GRAY8 or GRAY8) and returns a 8 bits gray scale image.

param da *DeviceAttribute* that contains the image
type da *DeviceAttribute*
param extract_as defaults to `ExtractAs.Numpy`
type extract_as *ExtractAs*
return the decoded data

- In case String string is chosen as extract method, a tuple is returned:
width<int>, height<int>, buffer<str>
- In case Numpy is chosen as extract method, a `numpy.ndarray` is returned with `ndim=2`, `shape=(height, width)` and `dtype=numpy.uint8`.
- In case Tuple or List are chosen, a tuple<tuple<int>> or list<list<int>> is returned.

Warning: The PyTango calls that return a *DeviceAttribute* (like *DeviceProxy.read_attribute()* or *DeviceProxy.command_inout()*) automatically extract the contents by default. This method requires that the given *DeviceAttribute* is obtained from a call which **DOESN'T** extract the contents. Example:

```
dev = tango.DeviceProxy("a/b/c")
da = dev.read_attribute("my_attr", extract_as=tango.ExtractAs.Nothing)
enc = tango.EncodedAttribute()
data = enc.decode_gray8(da)
```

decode_rgb32 (*da*, *extract_as*=<ExtensionMock name='_tango.ExtractAs.Numpy' id='140349536893440'>)

Decode a color image (JPEG_RGB or RGB24) and returns a 32 bits RGB image.

param da *DeviceAttribute* that contains the image

type da *DeviceAttribute*

param extract_as defaults to ExtractAs.Numpy

type extract_as ExtractAs

return the decoded data

- In case String string is choosen as extract method, a tuple is returned:
width<int>, height<int>, buffer<str>
- In case Numpy is choosen as extract method, a `numpy.ndarray` is returned with `ndim=2`, `shape=(height, width)` and `dtype=numpy.uint32`.
- In case Tuple or List are choosen, a tuple<tuple<int>> or list<list<int>> is returned.

Warning: The PyTango calls that return a *DeviceAttribute* (like *DeviceProxy.read_attribute()* or *DeviceProxy.command_inout()*) automatically extract the contents by default. This method requires that the given *DeviceAttribute* is obtained from a call which **DOESN'T** extract the contents. Example:

```
dev = tango.DeviceProxy("a/b/c")
da = dev.read_attribute("my_attr", extract_as=tango.ExtractAs.Nothing)
enc = tango.EncodedAttribute()
data = enc.decode_rgb32(da)
```

encode_gray16 (*gray16*, *width=0*, *height=0*)

Encode a 16 bit grayscale image (no compression)

param gray16 an object containing image information

type gray16 *str* or *buffer* or *numpy.ndarray* or *seq<element>*

param width image width. **MUST** be given if *gray16* is a string or if it is a *numpy.ndarray* with `ndims != 2`. Otherwise it is calculated internally.

type width *int*

param height image height. **MUST** be given if *gray16* is a string or if it is a *numpy.ndarray* with `ndims != 2`. Otherwise it is calculated internally.

type height *int*

Note: When *numpy.ndarray* is given:

- *gray16* **MUST** be CONTIGUOUS, ALIGNED
- if *gray16.ndims != 2*, *width* and *height* **MUST** be given and *gray16.nbytes/2* **MUST** match *width*height*
- if *gray16.ndims == 2*, *gray16.itemsize* **MUST** be 2 (typically, *gray16.dtype* is one of *numpy.dtype.int16*, *numpy.dtype.uint16*, *numpy.dtype.short* or *numpy.dtype.ushort*)

Example :

```
def read_myattr(self, attr):
    enc = tango.EncodedAttribute()
    data = numpy.arange(100, dtype=numpy.int16)
    data = numpy.array((data, data, data))
    enc.encode_gray16(data)
    attr.set_value(enc)
```

encode_gray8 (*gray8, width=0, height=0*)

Encode a 8 bit grayscale image (no compression)

param gray8 an object containing image information

type gray8 `str` or `numpy.ndarray` or `seq< seq<element> >`

param width image width. **MUST** be given if `gray8` is a string or if it is a `numpy.ndarray` with `ndims != 2`. Otherwise it is calculated internally.

type width `int`

param height image height. **MUST** be given if `gray8` is a string or if it is a `numpy.ndarray` with `ndims != 2`. Otherwise it is calculated internally.

type height `int`

Note: When `numpy.ndarray` is given:

- `gray8` **MUST** be CONTIGUOUS, ALIGNED
 - if `gray8.ndims != 2`, `width` and `height` **MUST** be given and `gray8.nbytes` **MUST** match `width*height`
 - if `gray8.ndims == 2`, `gray8.itemsize` **MUST** be 1 (typically, `gray8.dtype` is one of `numpy.dtype.byte`, `numpy.dtype.ubyte`, `numpy.dtype.int8` or `numpy.dtype.uint8`)
-

Example :

```
def read_myattr(self, attr):
    enc = tango.EncodedAttribute()
    data = numpy.arange(100, dtype=numpy.byte)
    data = numpy.array((data, data, data))
    enc.encode_gray8(data)
    attr.set_value(enc)
```

encode_jpeg_gray8 (*gray8, width=0, height=0, quality=100.0*)

Encode a 8 bit grayscale image as JPEG format

param gray8 an object containing image information

type gray8 `str` or `numpy.ndarray` or `seq< seq<element> >`

param width image width. **MUST** be given if `gray8` is a string or if it is a `numpy.ndarray` with `ndims != 2`. Otherwise it is calculated internally.

type width `int`

param height image height. **MUST** be given if `gray8` is a string or if it is a `numpy.ndarray` with `ndims != 2`. Otherwise it is calculated internally.

type height `int`

param quality Quality of JPEG (0=poor quality 100=max quality) (default is 100.0)

type quality `float`

Note: When `numpy.ndarray` is given:

- `gray8` **MUST** be CONTIGUOUS, ALIGNED
 - if `gray8.ndim` != 2, width and height **MUST** be given and `gray8.nbytes` **MUST** match `width*height`
 - if `gray8.ndim` == 2, `gray8.itemsize` **MUST** be 1 (typically, `gray8.dtype` is one of `numpy.dtype.byte`, `numpy.dtype.ubyte`, `numpy.dtype.int8` or `numpy.dtype.uint8`)
-

Example :

```
def read_myattr(self, attr):
    enc = tango.EncodedAttribute()
    data = numpy.arange(100, dtype=numpy.byte)
    data = numpy.array((data, data, data))
    enc.encode_jpeg_gray8(data)
    attr.set_value(enc)
```

encode_jpeg_rgb24 (`rgb24`, `width=0`, `height=0`, `quality=100.0`)

Encode a 24 bit rgb color image as JPEG format.

param rgb24 an object containing image information

type rgb24 `str` or `numpy.ndarray` or `seq< seq<element> >`

param width image width. **MUST** be given if `rgb24` is a string or if it is a `numpy.ndarray` with `ndim` != 3. Otherwise it is calculated internally.

type width `int`

param height image height. **MUST** be given if `rgb24` is a string or if it is a `numpy.ndarray` with `ndim` != 3. Otherwise it is calculated internally.

type height `int`

param quality Quality of JPEG (0=poor quality 100=max quality) (default is 100.0)

type quality `float`

Note: When `numpy.ndarray` is given:

- `rgb24` **MUST** be CONTIGUOUS, ALIGNED
 - if `rgb24.ndim` != 3, width and height **MUST** be given and `rgb24.nbytes/3` **MUST** match `width*height`
 - if `rgb24.ndim` == 3, `rgb24.itemsize` **MUST** be 1 (typically, `rgb24.dtype` is one of `numpy.dtype.byte`, `numpy.dtype.ubyte`, `numpy.dtype.int8` or `numpy.dtype.uint8`) and shape **MUST** be (`height`, `width`, 3)
-

Example :

```
def read_myattr(self, attr):
    enc = tango.EncodedAttribute()
    # create an 'image' where each pixel is R=0x01, G=0x01,
    ↪B=0x01
    arr = numpy.ones((10,10,3), dtype=numpy.uint8)
    enc.encode_jpeg_rgb24(data)
    attr.set_value(enc)
```

encode_jpeg_rgb32 (*rgb32, width=0, height=0, quality=100.0*)

Encode a 32 bit rgb color image as JPEG format.

param rgb32 an object containing image information

type rgb32 `str` or `numpy.ndarray` or `seq< seq<element> >`

param width image width. **MUST** be given if `rgb32` is a string or if it is a `numpy.ndarray` with `ndims != 2`. Otherwise it is calculated internally.

type width `int`

param height image height. **MUST** be given if `rgb32` is a string or if it is a `numpy.ndarray` with `ndims != 2`. Otherwise it is calculated internally.

type height `int`

Note: When `numpy.ndarray` is given:

- `rgb32` **MUST** be CONTIGUOUS, ALIGNED
 - if `rgb32.ndims != 2`, `width` and `height` **MUST** be given and `rgb32.nbytes/4` **MUST** match `width*height`
 - if `rgb32.ndims == 2`, `rgb32.itemsize` **MUST** be 4 (typically, `rgb32.dtype` is one of `numpy.dtype.int32`, `numpy.dtype.uint32`)
-

Example :

```
def read_myattr(self, attr):
    enc = tango.EncodedAttribute()
    data = numpy.arange(100, dtype=numpy.int32)
    data = numpy.array((data,data,data))
    enc.encode_jpeg_rgb32(data)
    attr.set_value(enc)
```

encode_rgb24 (*rgb24, width=0, height=0*)

Encode a 24 bit color image (no compression)

param rgb24 an object containing image information

type rgb24 `str` or `numpy.ndarray` or `seq< seq<element> >`

param width image width. **MUST** be given if `rgb24` is a string or if it is a `numpy.ndarray` with `ndims != 3`. Otherwise it is calculated internally.

type width `int`

param height image height. **MUST** be given if `rgb24` is a string or if it is a `numpy.ndarray` with `ndims != 3`. Otherwise it is calculated internally.

type height `int`

Note: When `numpy.ndarray` is given:

- `rgb24` **MUST** be CONTIGUOUS, ALIGNED
 - if `rgb24.ndim` != 3, width and height **MUST** be given and `rgb24.nbytes/3` **MUST** match `width*height`
 - if `rgb24.ndim` == 3, `rgb24.itemsize` **MUST** be 1 (typically, `rgb24.dtype` is one of `numpy.dtype.byte`, `numpy.dtype.ubyte`, `numpy.dtype.int8` or `numpy.dtype.uint8`) and shape **MUST** be (height, width, 3)
-

Example :

```
def read_myattr(self, attr):
    enc = tango.EncodedAttribute()
    # create an 'image' where each pixel is R=0x01, G=0x01,
    ↪B=0x01
    arr = numpy.ones((10,10,3), dtype=numpy.uint8)
    enc.encode_rgb24(data)
    attr.set_value(enc)
```

5.6 The Utilities API

```
class tango.utils.EventCallback (format='{date} {dev_name} {name} {type} {value}',
                                fd=<_io.TextIOWrapper name='<stdout>' mode='w'
                                encoding='utf-8'>, max_buf=100)
```

Useful event callback for test purposes

Usage:

```
>>> dev = tango.DeviceProxy(dev_name)
>>> cb = tango.utils.EventCallback()
>>> id = dev.subscribe_event("state", tango.EventType.CHANGE_EVENT, cb, [])
2011-04-06 15:33:18.910474 sys/tg_test/1 STATE CHANGE [ATTR_VALID] ON
```

Allowed format keys are:

- `date` (event timestamp)
- `reception_date` (event reception timestamp)
- `type` (event type)
- `dev_name` (device name)
- `name` (attribute name)
- `value` (event value)

New in PyTango 7.1.4

get_events()

Returns the list of events received by this callback

Returns the list of events received by this callback

Return type sequence<obj>

push_event (*evt*)

Internal usage only

`tango.utils.get_enum_labels` (*enum_cls*)

Return list of enumeration labels from Enum class.

The list is useful when creating an attribute, for the `enum_labels` parameter. The enumeration values are checked to ensure they are unique, start at zero, and increment by one.

Parameters `enum_cls` (`enum.Enum`) – the Enum class to be inspected

Returns List of label strings

Return type `list`

Raises **EnumTypeError** – in case the given class is invalid

`tango.utils.is_pure_str(obj)`

Tells if the given object is a python string.

In python 2.x this means any subclass of basestring. In python 3.x this means any subclass of str.

Parameters **obj** (`object`) – the object to be inspected

Returns True is the given obj is a string or False otherwise

Return type `bool`

`tango.utils.is_seq(obj)`

Tells if the given object is a python sequence.

It will return True for any collections.Sequence (list, tuple, str, bytes, unicode), bytearray and (if numpy is enabled) numpy.ndarray

Parameters **obj** (`object`) – the object to be inspected

Returns True is the given obj is a sequence or False otherwise

Return type `bool`

`tango.utils.is_non_str_seq(obj)`

Tells if the given object is a python sequence (excluding string sequences).

It will return True for any collections.Sequence (list, tuple (and bytes in python3)), bytearray and (if numpy is enabled) numpy.ndarray

Parameters **obj** (`object`) – the object to be inspected

Returns True is the given obj is a sequence or False otherwise

Return type `bool`

`tango.utils.is_integer(obj)`

Tells if the given object is a python integer.

It will return True for any int, long (in python 2) and (if numpy is enabled) numpy.integer

Parameters **obj** (`object`) – the object to be inspected

Returns True is the given obj is a python integer or False otherwise

Return type `bool`

`tango.utils.is_number(obj)`

Tells if the given object is a python number.

It will return True for any numbers.Number and (if numpy is enabled) numpy.number

Parameters **obj** (`object`) – the object to be inspected

Returns True is the given obj is a python number or False otherwise

Return type `bool`

`tango.utils.is_bool(tg_type, inc_array=False)`

Tells if the given tango type is boolean

Parameters

- **tg_type** (`tango.CmdArgType`) – tango type
- **inc_array** (`bool`) – (optional, default is False) determines if include array in the list of checked types

Returns True if the given tango type is boolean or False otherwise

Return type `bool`

`tango.utils.is_scalar_type` (*tg_type*)

Tells if the given tango type is a scalar

Parameters `tg_type` (*tango.CmdArgType*) – tango type

Returns True if the given tango type is a scalar or False otherwise

Return type `bool`

`tango.utils.is_array_type` (*tg_type*)

Tells if the given tango type is an array type

Parameters `tg_type` (*tango.CmdArgType*) – tango type

Returns True if the given tango type is an array type or False otherwise

Return type `bool`

`tango.utils.is_numerical_type` (*tg_type, inc_array=False*)

Tells if the given tango type is numerical

Parameters

- `tg_type` (*tango.CmdArgType*) – tango type
- `inc_array` (`bool`) – (optional, default is False) determines if include array in the list of checked types

Returns True if the given tango type is a numerical or False otherwise

Return type `bool`

`tango.utils.is_int_type` (*tg_type, inc_array=False*)

Tells if the given tango type is integer

Parameters

- `tg_type` (*tango.CmdArgType*) – tango type
- `inc_array` (`bool`) – (optional, default is False) determines if include array in the list of checked types

Returns True if the given tango type is integer or False otherwise

Return type `bool`

`tango.utils.is_float_type` (*tg_type, inc_array=False*)

Tells if the given tango type is float

Parameters

- `tg_type` (*tango.CmdArgType*) – tango type
- `inc_array` (`bool`) – (optional, default is False) determines if include array in the list of checked types

Returns True if the given tango type is float or False otherwise

Return type `bool`

`tango.utils.is_bool_type` (*tg_type, inc_array=False*)

Tells if the given tango type is boolean

Parameters

- `tg_type` (*tango.CmdArgType*) – tango type
- `inc_array` (`bool`) – (optional, default is False) determines if include array in the list of checked types

Returns True if the given tango type is boolean or False otherwise

Return type `bool`

`tango.utils.is_binary_type` (*tg_type, inc_array=False*)

Tells if the given tango type is binary

Parameters

- **tg_type** (*tango.CmdArgType*) – tango type
- **inc_array** (*bool*) – (optional, default is False) determines if include array in the list of checked types

Returns True if the given tango type is binary or False otherwise

Return type *bool*

`tango.utils.is_str_type` (*tg_type, inc_array=False*)

Tells if the given tango type is string

Parameters

- **tg_type** (*tango.CmdArgType*) – tango type
- **inc_array** (*bool*) – (optional, default is False) determines if include array in the list of checked types

Returns True if the given tango type is string or False otherwise

Return type *bool*

`tango.utils.obj_2_str` (*obj, tg_type=None*)

Converts a python object into a string according to the given tango type

Parameters

- **obj** (*object*) – the object to be converted
- **tg_type** (*tango.CmdArgType*) – tango type

Returns a string representation of the given object

Return type *str*

`tango.utils.seqStr_2_obj` (*seq, tg_type, tg_format=None*)

Translates a sequence<str> to a sequence of objects of give type and format

Parameters

- **seq** (*sequence<str>*) – the sequence
- **tg_type** (*tango.CmdArgType*) – tango type
- **tg_format** (*tango.AttrDataFormat*) – (optional, default is None, meaning SCALAR) tango format

Returns a new sequence

`tango.utils.scalar_to_array_type` (*tg_type*)

Gives the array tango type corresponding to the given tango scalar type. Example: giving Dev-Long will return DevVarLongArray.

Parameters **tg_type** (*tango.CmdArgType*) – tango type

Returns the array tango type for the given scalar tango type

Return type *tango.CmdArgType*

Raises **ValueError** – in case the given dtype is not a tango scalar type

`tango.utils.get_home` ()

Find user's home directory if possible. Otherwise raise error.

Returns user's home directory

Return type *str*

New in PyTango 7.1.4

`tango.utils.requires_pyango` (*min_version=None, conflicts=(), software_name='Software'*)

Determines if the required PyTango version for the running software is present. If not an exception is thrown. Example usage:

```
from tango import requires_pyango

requires_pyango('7.1', conflicts=['8.1.1'], software='MyDS')
```

Parameters

- **min_version** (*None, str, LooseVersion*) – minimum PyTango version [default: *None*, meaning no minimum required]. If a string is given, it must be in the valid version number format (see: *LooseVersion*)
- **conflicts** (*seq<str/LooseVersion>*) – a sequence of PyTango versions which conflict with the software using it
- **software_name** (*str*) – software name using tango. Used in the exception message

Raises **Exception** – if the required PyTango version is not met

New in PyTango 8.1.4

`tango.utils.requires_tango` (*min_version=None, conflicts=(), software_name='Software'*)
Determines if the required Tango version for the running software is present. If not an exception is thrown. Example usage:

```
from tango import requires_tango

requires_tango('7.1', conflicts=['8.1.1'], software='MyDS')
```

Parameters

- **min_version** (*None, str, LooseVersion*) – minimum Tango version [default: *None*, meaning no minimum required]. If a string is given, it must be in the valid version number format (see: *LooseVersion*)
- **conflicts** (*seq<str/LooseVersion>*) – a sequence of Tango versions which conflict with the software using it
- **software_name** (*str*) – software name using Tango. Used in the exception message

Raises **Exception** – if the required Tango version is not met

New in PyTango 8.1.4

5.7 Exception API

5.7.1 Exception definition

All the exceptions that can be thrown by the underlying Tango C++ API are available in the PyTango python module. Hence a user can catch one of the following exceptions:

- *DevFailed*
- *ConnectionFailed*
- *CommunicationFailed*
- *WrongNameSyntax*
- *NonDbDevice*
- *WrongData*
- *NonSupportedFeature*
- *AsynCall*

- `AsynReplyNotArrived`
- `EventSystemFailed`
- `NamedDevFailedList`
- `DeviceUnlocked`

When an exception is caught, the `sys.exc_info()` function returns a tuple of three values that give information about the exception that is currently being handled. The values returned are (type, value, traceback). Since most functions don't need access to the traceback, the best solution is to use something like `exctype, value = sys.exc_info()[:2]` to extract only the exception type and value. If one of the Tango exceptions is caught, the `exctype` will be class name of the exception (`DevFailed`, .. etc) and the value a tuple of dictionary objects all of which containing the following kind of key-value pairs:

- **reason**: a string describing the error type (more readable than the associated error code)
- **desc**: a string describing in plain text the reason of the error.
- **origin**: a string giving the name of the (C++ API) method which thrown the exception
- **severity**: one of the strings `WARN`, `ERR`, `PANIC` giving severity level of the error.

```
1 import tango
2
3 # How to protect the script from exceptions raised by the Tango
4 try:
5     # Get proxy on a non existing device should throw an exception
6     device = tango.DeviceProxy("non/existing/device")
7 except DevFailed as df:
8     print("Failed to create proxy to non/existing/device:\n%s" % df)
```

5.7.2 Throwing exception in a device server

The C++ `tango::Except` class with its most important methods have been wrapped to Python. Therefore, in a Python device server, you have the following methods to throw, re-throw or print a `Tango::DevFailed` exception :

- `throw_exception()` which is a static method
- `re_throw_exception()` which is also a static method
- `print_exception()` which is also a static method

The following code is an example of a command method requesting a command on a sub-device and re-throwing the exception in case of:

```
1 try:
2     dev.command_inout("SubDevCommand")
3 except tango.DevFailed as df:
4     tango.Except.re_throw_exception(df,
5         "MyClass_CommandFailed",
6         "Sub device command SubdevCommand failed",
7         "Command() ")
```

line 2 Send the command to the sub device in a try/catch block

line 4-6 Re-throw the exception and add a new level of information in the exception stack

5.7.3 Exception API

class tango.**Except**

A container for the static methods:

- `throw_exception`
- `re_throw_exception`
- `print_exception`
- `compare_exception`

class tango.**DevError**

Structure describing any error resulting from a command execution, or an attribute query, with following members:

- `reason` : (*str*) reason
- `severity` : (*ErrSeverity*) error severity (WARN, ERR, PANIC)
- `desc` : (*str*) error description
- `origin` : (*str*) Tango server method in which the error happened

exception tango.**DevFailed**

exception tango.**ConnectionFailed**

This exception is thrown when a problem occurs during the connection establishment between the application and the device. The API is stateless. This means that DeviceProxy constructors filter most of the exception except for cases described in the following table.

The desc DevError structure field allows a user to get more precise information. These informations are :

DB_DeviceNotDefined The name of the device not defined in the database

API_CommandFailed The device and command name

API_CantConnectToDevice The device name

API_CorbaException The name of the CORBA exception, its reason, its locality, its completed flag and its minor code

API_CantConnectToDatabase The database server host and its port number

API_DeviceNotExported The device name

exception tango.**CommunicationFailed**

This exception is thrown when a communication problem is detected during the communication between the client application and the device server. It is a two levels Tango::DevError structure. In case of time-out, the DevError structures fields are:

Level	Reason	Desc	Severity
0	API_CorbaException	CORBA exception fields translated into a string	ERR
1	API_DeviceTimedOut	String with time-out value and device name	ERR

For all other communication errors, the DevError structures fields are:

Level	Reason	Desc	Severity
0	API_CorbaException	CORBA exception fields translated into a string	ERR
1	API_CommunicationFailed	String with device, method, command/attribute name	ERR

exception tango.**WrongNameSyntax**

This exception has only one level of Tango::DevError structure. The possible value for the reason field are :

API_UnsupportedProtocol This error occurs when trying to build a DeviceProxy or an AttributeProxy instance for a device with an unsupported protocol. Refer to the appendix on device naming syntax to get the list of supported database modifier

API_UnsupportedDBaseModifier This error occurs when trying to build a DeviceProxy or an AttributeProxy instance for a device/attribute with a database modifier unsupported. Refer to the appendix on device naming syntax to get the list of supported database modifier

API_WrongDeviceNameSyntax This error occurs for all the other error in device name syntax. It is thrown by the DeviceProxy class constructor.

API_WrongAttributeNameSyntax This error occurs for all the other error in attribute name syntax. It is thrown by the AttributeProxy class constructor.

API_WrongWildcardUsage This error occurs if there is a bad usage of the wildcard character

exception `tango.NonDbDevice`

This exception has only one level of Tango::DevError structure. The reason field is set to `API_NonDatabaseDevice`. This exception is thrown by the API when using the DeviceProxy or AttributeProxy class database access for non-database device.

exception `tango.WrongData`

This exception has only one level of Tango::DevError structure. The possible value for the reason field are :

API_EmptyDbDatum This error occurs when trying to extract data from an empty DbDatum object

API_IncompatibleArgumentType This error occurs when trying to extract data with a type different than the type used to send the data

API_EmptyDeviceAttribute This error occurs when trying to extract data from an empty DeviceAttribute object

API_IncompatibleAttrArgumentType This error occurs when trying to extract attribute data with a type different than the type used to send the data

API_EmptyDeviceData This error occurs when trying to extract data from an empty DeviceData object

API_IncompatibleCmdArgumentType This error occurs when trying to extract command data with a type different than the type used to send the data

exception `tango.NonSupportedFeature`

This exception is thrown by the API layer when a request to a feature implemented in Tango device interface release n is requested for a device implementing Tango device interface n-x. There is one possible value for the reason field which is `API_UnsupportedFeature`.

exception `tango.AsynCall`

This exception is thrown by the API layer when a the asynchronous model id badly used. This exception has only one level of Tango::DevError structure. The possible value for the reason field are :

API_BadAsynPollId This error occurs when using an asynchronous request identifier which is not valid any more.

API_BadAsyn This error occurs when trying to fire callback when no callback has been previously registered

API_BadAsynReqType This error occurs when trying to get result of an asynchronous request with an asynchronous request identifier returned by a

non-coherent asynchronous request (For instance, using the asynchronous request identifier returned by a `command_inout_async()` method with a `read_attribute_reply()` attribute).

exception `tango.AsynReplyNotArrived`

This exception is thrown by the API layer when:

- a request to get asynchronous reply is made and the reply is not yet arrived
- a blocking wait with timeout for asynchronous reply is made and the timeout expired.

There is one possible value for the reason field which is `API_AsynReplyNotArrived`.

exception `tango.EventSystemFailed`

This exception is thrown by the API layer when subscribing or unsubscribing from an event failed. This exception has only one level of `Tango::DevError` structure. The possible value for the reason field are :

API_NotificationServiceFailed This error occurs when the `subscribe_event()` method failed trying to access the CORBA notification service

API_EventNotFound This error occurs when you are using an incorrect `event_id` in the `unsubscribe_event()` method

API_InvalidArgs This error occurs when NULL pointers are passed to the `subscribe` or `unsubscribe` event methods

API_MethodArgument This error occurs when trying to subscribe to an event which has already been subscribed to

API_DSFailedRegisteringEvent This error means that the device server to which the device belongs to failed when it tries to register the event. Most likely, it means that there is no event property defined

API_EventNotFound Occurs when using a wrong event identifier in the `unsubscribe_event` method

exception `tango.DeviceUnlocked`

This exception is thrown by the API layer when a device locked by the process has been unlocked by an admin client. This exception has two levels of `Tango::DevError` structure. There is only possible value for the reason field which is

API_DeviceUnlocked The device has been unlocked by another client (administration client)

The first level is the message reported by the Tango kernel from the server side. The second layer is added by the client API layer with informations on which API call generates the exception and device name.

exception `tango.NotAllowed`

exception `tango.NamedDevFailedList`

This exception is only thrown by the `DeviceProxy::write_attributes()` method. In this case, it is necessary to have a new class of exception to transfer the error stack for several attribute(s) which failed during the writing. Therefore, this exception class contains for each attributes which failed :

- The name of the attribute
- Its index in the vector passed as argument of the `write_attributes()` method
- The error stack

This is a small list of how-tos specific to PyTango. A more general Tango how-to list can be found [here](#).

6.1 How to contribute

Everyone is welcome to contribute to PyTango project. If you don't feel comfortable with writing core PyTango we are looking for contributors to documentation or/and tests.

It refers to the next section, see *How to Contribute*.

6.2 Check the default TANGO host

The default TANGO host can be defined using the environment variable `TANGO_HOST` or in a *tangorc* file (see [Tango environment variables](#) for complete information)

To check what is the current value that TANGO uses for the default configuration simple do:

```
1 >>> import tango
2 >>> tango.ApiUtil.get_env_var("TANGO_HOST")
3 'homer.simpson.com:10000'
```

6.3 Check TANGO version

There are two library versions you might be interested in checking: The PyTango version:

```
1 >>> import tango
2 >>> tango.__version__
3 '9.3.2'
4 >>> tango.__version_info__
5 (9, 3, 2)
```

and the Tango C++ library version that PyTango was compiled with:

```
1 >>> import tango
2 >>> tango.constants.TgLibVers
3 '9.3.3'
```

6.4 Report a bug

Bugs can be reported as issues in [PyTango Github](#).

It is also helpful if you can put in the issue description the PyTango information. It can be a dump of:

```
$ python -c "from tango.utils import info; print(info())"
```

6.5 Test the connection to the Device and get it's current state

One of the most basic examples is to get a reference to a device and determine if it is running or not:

```
1 from tango import DeviceProxy
2
3 # Get proxy on the tango_test1 device
4 print("Creating proxy to TangoTest device...")
5 tango_test = DeviceProxy("sys/tg_test/1")
6
7 # ping it
8 print(tango_test.ping())
9
10 # get the state
11 print(tango_test.state())
```

6.6 Read and write attributes

Basic read/write attribute operations:

```
1 from tango import DeviceProxy
2
3 # Get proxy on the tango_test1 device
4 print("Creating proxy to TangoTest device...")
5 tango_test = DeviceProxy("sys/tg_test/1")
6
7 # Read a scalar attribute. This will return a tango.DeviceAttribute
8 # Member 'value' contains the attribute value
9 scalar = tango_test.read_attribute("long_scalar")
10 print("Long_scalar value = {0}".format(scalar.value))
11
12 # PyTango provides a shorter way:
13 scalar = tango_test.long_scalar
14 print("Long_scalar value = {0}".format(scalar))
15
16 # Read a spectrum attribute
17 spectrum = tango_test.read_attribute("double_spectrum")
18 # ... or, the shorter version:
19 spectrum = tango_test.double_spectrum
20
21 # Write a scalar attribute
22 scalar_value = 18
23 tango_test.write_attribute("long_scalar", scalar_value)
24
25 # PyTango provides a shorter way:
26 tango_test.long_scalar = scalar_value
27
28 # Write a spectrum attribute
29 spectrum_value = [1.2, 3.2, 12.3]
```

(continues on next page)

(continued from previous page)

```

30 tango_test.write_attribute("double_spectrum", spectrum_value)
31 # ... or, the shorter version:
32 tango_test.double_spectrum = spectrum_value
33
34 # Write an image attribute
35 image_value = [ [1, 2], [3, 4] ]
36 tango_test.write_attribute("long_image", image_value)
37 # ... or, the shorter version:
38 tango_test.long_image = image_value

```

Note that if PyTango is compiled with numpy support the values got when reading a spectrum or an image will be numpy arrays. This results in a faster and more memory efficient PyTango. You can also use numpy to specify the values when writing attributes, especially if you know the exact attribute type:

```

1  import numpy
2  from tango import DeviceProxy
3
4  # Get proxy on the tango_test1 device
5  print("Creating proxy to TangoTest device...")
6  tango_test = DeviceProxy("sys/tg_test/1")
7
8  data_1d_long = numpy.arange(0, 100, dtype=numpy.int32)
9
10 tango_test.long_spectrum = data_1d_long
11
12 data_2d_float = numpy.zeros((10,20), dtype=numpy.float64)
13
14 tango_test.double_image = data_2d_float

```

6.7 Execute commands

As you can see in the following example, when scalar types are used, the Tango binding automatically manages the data types, and writing scripts is quite easy:

```

1  from tango import DeviceProxy
2
3  # Get proxy on the tango_test1 device
4  print("Creating proxy to TangoTest device...")
5  tango_test = DeviceProxy("sys/tg_test/1")
6
7  # First use the classical command_inout way to execute the DevString command
8  # (DevString in this case is a command of the Tango_Test device)
9
10 result = tango_test.command_inout("DevString", "First hello to device")
11 print("Result of execution of DevString command = {0}".format(result))
12
13 # the same can be achieved with a helper method
14 result = tango_test.DevString("Second Hello to device")
15 print("Result of execution of DevString command = {0}".format(result))
16
17 # Please note that argin argument type is automatically managed by python
18 result = tango_test.DevULong(12456)
19 print("Result of execution of DevULong command = {0}".format(result))

```

6.8 Execute commands with more complex types

In this case you have to use put your arguments data in the correct python structures:

```
1 from tango import DeviceProxy
2
3 # Get proxy on the tango_test1 device
4 print("Creating proxy to TangoTest device...")
5 tango_test = DeviceProxy("sys/tg_test/1")
6
7 # The input argument is a DevVarLongStringArray so create the argin
8 # variable containing an array of longs and an array of strings
9 argin = ([1,2,3], ["Hello", "TangoTest device"])
10
11 result = tango_test.DevVarLongStringArray(argin)
12 print("Result of execution of DevVarLongArray command = {0}".format(result))
```

6.9 Work with Groups

Todo: write this how to

6.10 Handle errors

Todo: write this how to

For now check *Exception API*.

6.11 Registering devices

Here is how to define devices in the Tango DataBase:

```
1 from tango import Database, DbDevInfo
2
3 # A reference on the DataBase
4 db = Database()
5
6 # The 3 devices name we want to create
7 # Note: these 3 devices will be served by the same DServer
8 new_device_name1 = "px1/tdl/mouse1"
9 new_device_name2 = "px1/tdl/mouse2"
10 new_device_name3 = "px1/tdl/mouse3"
11
12 # Define the Tango Class served by this DServer
13 new_device_info_mouse = DbDevInfo()
14 new_device_info_mouse._class = "Mouse"
15 new_device_info_mouse.server = "ds_Mouse/server_mouse"
16
17 # add the first device
18 print("Creating device: %s" % new_device_name1)
19 new_device_info_mouse.name = new_device_name1
20 db.add_device(new_device_info_mouse)
```

(continues on next page)

(continued from previous page)

```

21
22 # add the next device
23 print("Creating device: %s" % new_device_name2)
24 new_device_info_mouse.name = new_device_name2
25 db.add_device(new_device_info_mouse)
26
27 # add the third device
28 print("Creating device: %s" % new_device_name3)
29 new_device_info_mouse.name = new_device_name3
30 db.add_device(new_device_info_mouse)

```

6.11.1 Setting up device properties

A more complex example using python subtleties. The following python script example (containing some functions and instructions manipulating a Galil motor axis device server) gives an idea of how the Tango API should be accessed from Python:

```

1  from tango import DeviceProxy
2
3  # connecting to the motor axis device
4  axis1 = DeviceProxy("microxas/motorisation/galilbox")
5
6  # Getting Device Properties
7  property_names = ["AxisBoxAttachement",
8                   "AxisEncoderType",
9                   "AxisNumber",
10                  "CurrentAcceleration",
11                  "CurrentAccuracy",
12                  "CurrentBacklash",
13                  "CurrentDeceleration",
14                  "CurrentDirection",
15                  "CurrentMotionAccuracy",
16                  "CurrentOvershoot",
17                  "CurrentRetry",
18                  "CurrentScale",
19                  "CurrentSpeed",
20                  "CurrentVelocity",
21                  "EncoderMotorRatio",
22                  "logging_level",
23                  "logging_target",
24                  "UserEncoderRatio",
25                  "UserOffset"]
26
27  axis_properties = axis1.get_property(property_names)
28  for prop in axis_properties.keys():
29      print("%s: %s" % (prop, axis_properties[prop][0]))
30
31  # Changing Properties
32  axis_properties["AxisBoxAttachement"] = ["microxas/motorisation/galilbox"]
33  axis_properties["AxisEncoderType"] = ["1"]
34  axis_properties["AxisNumber"] = ["6"]
35  axis1.put_property(axis_properties)

```

6.12 Using clients with multiprocessing

Since version 9.3.0 PyTango provides `cleanup()` which resets CORBA connection. This static function is needed when you want to use `tango` with `multiprocessing` in your client code.

In the case when both your parent process and your child process create `DeviceProxy`, `Database` or/and `AttributeProxy` your child process inherits the context from your parent process, i.e. open file descriptors, the TANGO and the CORBA state. Sharing the above objects between the processes may cause unpredictable errors, e.g. `TRANSIENT_CallTimeout`, `unidentifiable C++ exception`. Therefore, when you start a new process you must reset CORBA connection:

```

1 import time
2 import tango
3
4 from multiprocessing import Process
5
6
7 class Worker(Process):
8
9     def __init__(self):
10         Process.__init__(self)
11
12     def run(self):
13         # reset CORBA connection
14         tango.ApiUtil.cleanup()
15
16         proxy = tango.DeviceProxy('test/tserver/1')
17
18         stime = time.time()
19         etime = stime
20         while etime - stime < 1.:
21             try:
22                 proxy.read_attribute("Value")
23             except Exception as e:
24                 print(str(e))
25             etime = time.time()
26
27
28 def runworkers():
29     workers = [Worker() for _ in range(6)]
30     for wk in workers:
31         wk.start()
32     for wk in workers:
33         wk.join()
34
35
36 db = tango.Database()
37 dp = tango.DeviceProxy('test/tserver/1')
38
39 for i in range(4):
40     runworkers()

```

After `cleanup()` all references to `DeviceProxy`, `AttributeProxy` or `Database` objects in the current process become invalid and these objects need to be reconstructed.

6.13 Using clients with multithreading

When performing Tango I/O from user-created threads, there can be problems. This is often more noticeable with event subscription and unsubscription, but it could affect any Tango I/O. As PyTango wraps the cppTango library, we need to consider how cppTango's threads work.

cppTango was originally developed at a time where C++ didn't have standard threads. All the threads currently created in cppTango are omni threads, since this is what the omniORB library is using to create threads and since this implementation is available for free with omniORB.

In C++, users used to create omni threads in the past so there was no issue. Since C++11, C++ comes with an implementation of standard threads. cppTango is currently (version 9.3.3) not directly thread safe when a user is using C++11 standard threads or threads different than omni threads. This lack of thread safety includes threads created from Python's `threading` module.

In an ideal future cppTango should protect itself, regardless of what type of threads are used. In the meantime, we need a work-around.

The work-around when using threads which are not omni threads is to create an object of the C++ class `omni_thread::ensure_self` in the user thread, just after the thread creation, and to delete this object only when the thread has finished its job. This `omni_thread::ensure_self` object provides a dummy omniORB ID for the thread. This ID is used when accessing thread locks within cppTango, so the ID must remain the same for the lifetime of the thread. Also note that this object **MUST** be released before the thread has exited, otherwise omniORB will throw an exception.

A Pythonic way to implement this work-around for multithreaded applications is available via the `EnsureOmniThread` class. It was added in PyTango version 9.3.2. This class is best used as a context handler to wrap the target method of the user thread. An example is shown below:

```

1 import tango
2 from threading import Thread
3 from time import sleep
4
5
6 def thread_task():
7     with tango.EnsureOmniThread():
8         eid = dp.subscribe_event(
9             "double_scalar", tango.EventType.PERIODIC_EVENT, cb)
10        while running:
11            print("num events stored {}".format(len(cb.get_events())))
12            sleep(1)
13        dp.unsubscribe_event(eid)
14
15
16 cb = tango.utils.EventCallback() # print events to stdout
17 dp = tango.DeviceProxy("sys/tg_test/1")
18 dp.poll_attribute("double_scalar", 1000)
19 thread = Thread(target=thread_task)
20 running = True
21 thread.start()
22 sleep(5)
23 running = False
24 thread.join()

```

Another way to create threads in Python is the `concurrent.futures.ThreadPoolExecutor`. The problem with this is that the API does not provide an easy way for the context handler to cover the lifetime of the threads, which are created as daemons. One option is to at least use the context handler for the functions that are submitted to the executor. I.e., `executor.submit(thread_task)`. This is not guaranteed to work. A second option to investigate (if using at least Python 3.7) is the `initializer` argument which could be used to ensure a call to the `__enter__()` method for a thread-specific instance of `EnsureOmniThread`. However, calling the `__exit__()` method on the corresponding object at shutdown is a problem. Maybe it could be submitted as work.

6.14 Write a server

Before reading this chapter you should be aware of the TANGO basic concepts. This chapter does not explain what a Tango device or a device server is. This is explained in detail in the [Tango control system manual](#)

Since version 8.1, PyTango provides a helper module which simplifies the development of a Tango device server. This helper is provided through the `tango.server` module.

Here is a simple example on how to write a *Clock* device server using the high level API

```

1  import time
2  from tango.server import Device, attribute, command, pipe
3
4
5  class Clock(Device):
6
7      @attribute
8      def time(self):
9          return time.time()
10
11     @command(dtype_in=str, dtype_out=str)
12     def strftime(self, format):
13         return time.strftime(format)
14
15     @pipe
16     def info(self):
17         return ('Information',
18                dict(manufacturer='Tango',
19                    model='PS2000',
20                    version_number=123))
21
22
23  if __name__ == "__main__":
24      Clock.run_server()

```

line 2 import the necessary symbols

line 5 tango device class definition. A Tango device must inherit from `tango.server.Device`

line 7-9 definition of the *time* attribute. By default, attributes are double, scalar, read-only. Check the [attribute](#) for the complete list of attribute options.

line 11-13 the method *strftime* is exported as a Tango command. It receives a string as argument and it returns a string. If a method is to be exported as a Tango command, it must be decorated as such with the `command()` decorator

line 15-20 definition of the *info* pipe. Check the [pipe](#) for the complete list of pipe options.

line 24 start the Tango run loop. This method automatically determines the Python class name and exports it as a Tango class. For more complicated cases, check `run()` for the complete list of options

There is a more detailed clock device server in the examples/Clock folder.

Here is a more complete example on how to write a *PowerSupply* device server using the high level API. The example contains:

1. a read-only double scalar attribute called *voltage*
2. a read/write double scalar expert attribute *current*
3. a read-only double image attribute called *noise*
4. a *ramp* command
5. a *host* device property

6. a *port* class property

```

1 from time import time
2 from numpy.random import random_sample
3
4 from tango import AttrQuality, AttrWriteType, DispLevel
5 from tango.server import Device, attribute, command
6 from tango.server import class_property, device_property
7
8
9 class PowerSupply(Device):
10
11     current = attribute(label="Current", dtype=float,
12                        display_level=DispLevel.EXPERT,
13                        access=AttrWriteType.READ_WRITE,
14                        unit="A", format="8.4f",
15                        min_value=0.0, max_value=8.5,
16                        min_alarm=0.1, max_alarm=8.4,
17                        min_warning=0.5, max_warning=8.0,
18                        fget="get_current", fset="set_current",
19                        doc="the power supply current")
20
21     noise = attribute(label="Noise", dtype=((float,)),
22                      max_dim_x=1024, max_dim_y=1024,
23                      fget="get_noise")
24
25     host = device_property(dtype=str)
26     port = class_property(dtype=int, default_value=9788)
27
28     @attribute
29     def voltage(self):
30         self.info_stream("get voltage(%s, %d)" % (self.host, self.port))
31         return 10.0
32
33     def get_current(self):
34         return 2.3456, time(), AttrQuality.ATTR_WARNING
35
36     def set_current(self, current):
37         print("Current set to %f" % current)
38
39     def get_noise(self):
40         return random_sample((1024, 1024))
41
42     @command(dtype_in=float)
43     def ramp(self, value):
44         print("Ramping up...")
45
46
47 if __name__ == "__main__":
48     PowerSupply.run_server()

```

6.15 Server logging

This chapter instructs you on how to use the tango logging API (log4tango) to create tango log messages on your device server.

The logging system explained here is the Tango Logging Service (TLS). For detailed information on how this logging system works please check:

- [3.5 The tango logging service](#)
- [9.3 The tango logging service](#)

The easiest way to start seeing log messages on your device server console is by starting it with the verbose option. Example:

```
python PyDsExp.py PyDs1 -v4
```

This activates the console tango logging target and filters messages with importance level DEBUG or more. The links above provided detailed information on how to configure log levels and log targets. In this document we will focus on how to write log messages on your device server.

6.15.1 Basic logging

The most basic way to write a log message on your device is to use the *Device* logging related methods:

- `debug_stream()`
- `info_stream()`
- `warn_stream()`
- `error_stream()`
- `fatal_stream()`

Example:

```
1 def read_voltage(self):
2     self.info_stream("read voltage attribute")
3     # ...
4     return voltage_value
```

This will print a message like:

```
1282206864 [-1215867200] INFO test/power_supply/1 read voltage attribute
```

every time a client asks to read the *voltage* attribute value.

The logging methods support argument list feature (since PyTango 8.1). Example:

```
1 def read_voltage(self):
2     self.info_stream("read_voltage(%s, %d)", self.host, self.port)
3     # ...
4     return voltage_value
```

6.15.2 Logging with print statement

This feature is only possible since PyTango 7.1.3

It is possible to use the print statement to log messages into the tango logging system. This is achieved by using the python's print extend form sometimes referred to as *print chevron*.

Same example as above, but now using *print chevron*:

```
1 def read_voltage(self, the_att):
2     print >>self.log_info, "read voltage attribute"
3     # ...
4     return voltage_value
```

Or using the python 3k print function:

```
1 def read_Long_attr(self, the_att):
2     print("read voltage attribute", file=self.log_info)
3     # ...
4     return voltage_value
```

6.15.3 Logging with decorators

This feature is only possible since PyTango 7.1.3

PyTango provides a set of decorators that place automatic log messages when you enter and when you leave a python method. For example:

```
1 @tango.DebugIt()
2 def read_Long_attr(self, the_att):
3     the_att.set_value(self.attr_long)
```

will generate a pair of log messages each time a client asks for the 'Long_attr' value. Your output would look something like:

```
1282208997 [-1215965504] DEBUG test/pydsexp/1 -> read_Long_attr()
1282208997 [-1215965504] DEBUG test/pydsexp/1 <- read_Long_attr()
```

Decorators exist for all tango log levels:

- *tango.DebugIt*
- *tango.InfoIt*
- *tango.WarnIt*
- *tango.ErrorIt*
- *tango.FatalIt*

The decorators receive three optional arguments:

- *show_args* - shows method arguments in log message (defaults to False)
- *show_kwargs* shows keyword method arguments in log message (defaults to False)
- *show_ret* - shows return value in log message (defaults to False)

Example:

```
1 @tango.DebugIt(show_args=True, show_ret=True)
2 def IOLong(self, in_data):
3     return in_data * 2
```

will output something like:

```
1282221947 [-1261438096] DEBUG test/pydsexp/1 -> IOLong(23)
1282221947 [-1261438096] DEBUG test/pydsexp/1 46 <- IOLong()
```

6.16 Multiple device classes (Python and C++) in a server

Within the same python interpreter, it is possible to mix several Tango classes. Let's say two of your colleagues programmed two separate Tango classes in two separated python files: A PLC class in a PLC.py:

```
1 # PLC.py
2
3 from tango.server import Device
4
5 class PLC(Device):
6
7     # bla, bla my PLC code
8
9 if __name__ == "__main__":
10     PLC.run_server()
```

... and a IRMirror in a IRMirror.py:

```
1 # IRMirror.py
2
3 from tango.server import Device
4
5 class IRMirror(Device):
6
7     # bla, bla my IRMirror code
8
9 if __name__ == "__main__":
10     IRMirror.run_server()
```

You want to create a Tango server called *PLCMirror* that is able to contain devices from both PLC and IRMirror classes. All you have to do is write a *PLCMirror.py* containing the code:

```
1 # PLCMirror.py
2
3 from tango.server import run
4 from PLC import PLC
5 from IRMirror import IRMirror
6
7 run([PLC, IRMirror])
```

It is also possible to add C++ Tango class in a Python device server as soon as:

1. The Tango class is in a shared library
2. It exist a C function to create the Tango class

For a Tango class called *MyTgClass*, the shared library has to be called *MyTgClass.so* and has to be in a directory listed in the `LD_LIBRARY_PATH` environment variable. The C function creating the Tango class has to be called `_create_MyTgClass_class()` and has to take one parameter of type "char *" which is the Tango class name. Here is an example of the main function of the same device server than before but with one C++ Tango class called *SerialLine*:

```
1 import tango
2 import sys
3
```

(continues on next page)

(continued from previous page)

```

4  if __name__ == '__main__':
5      py = tango.Util(sys.argv)
6      util.add_class('SerialLine', 'SerialLine', language="c++")
7      util.add_class(PLCClass, PLC, 'PLC')
8      util.add_class(IRMirrorClass, IRMirror, 'IRMirror')
9
10     U = tango.Util.instance()
11     U.server_init()
12     U.server_run()

```

Line 6 The C++ class is registered in the device server

Line 7 and 8 The two Python classes are registered in the device server

6.17 Create attributes dynamically

It is also possible to create dynamic attributes within a Python device server. There are several ways to create dynamic attributes. One of the way, is to create all the devices within a loop, then to create the dynamic attributes and finally to make all the devices available for the external world. In C++ device server, this is typically done within the <Device>Class::device_factory() method. In Python device server, this method is generic and the user does not have one. Nevertheless, this generic device_factory method calls a method named dyn_attr() allowing the user to create his dynamic attributes. It is simply necessary to re-define this method within your <Device>Class and to create the dynamic attribute within this method:

```
dyn_attr(self, dev_list)
```

where dev_list is a list containing all the devices created by the generic device_factory() method.

There is another point to be noted regarding dynamic attribute within Python device server. The Tango Python device server core checks that for each attribute it exists methods named <attribute_name>_read and/or <attribute_name>_write and/or is_<attribute_name>_allowed. Using dynamic attribute, it is not possible to define these methods because attributes name and number are known only at run-time. To address this issue, the Device_3Impl::add_attribute() method has a diferent signature for Python device server which is:

```
add_attribute(self, attr, r_meth = None, w_meth = None,
is_allo_meth = None)
```

attr is an instance of the Attr class, r_meth is the method which has to be executed with the attribute is read, w_meth is the method to be executed when the attribute is written and is_allo_meth is the method to be executed to implement the attribute state machine. The method passed here as argument as to be class method and not object method. Which argument you have to use depends on the type of the attribute (A WRITE attribute does not need a read method). Note, that depending on the number of argument you pass to this method, you may have to use Python keyword argument. The necessary methods required by the Tango Python device server core will be created automatically as a forward to the methods given as arguments.

Here is an example of a device which has a TANGO command called *createFloatAttribute*. When called, this command creates a new scalar floating point attribute with the specified name:

```

1  from tango import Util, Attr, AttrWriteType
2  from tango.server import Device, command
3
4  class MyDevice(Device):
5
6      @command(dtype_in=str)
7      def CreateFloatAttribute(self, attr_name):

```

(continues on next page)

(continued from previous page)

```

8     attr = Attr(attr_name, tango.DevDouble, AttrWriteType.READ_WRITE)
9     self.add_attribute(attr, self.read_General, self.write_General)
10
11     def read_General(self, attr):
12         self.info_stream("Reading attribute %s", attr.get_name())
13         attr.set_value(99.99)
14
15     def write_General(self, attr):
16         self.info_stream("Writting attribute %s", attr.get_name())

```

6.18 Create/Delete devices dynamically

This feature is only possible since PyTango 7.1.2

Starting from PyTango 7.1.2 it is possible to create devices in a device server “en caliente”. This means that you can create a command in your “management device” of a device server that creates devices of (possibly) several other tango classes. There are two ways to create a new device which are described below.

Tango imposes a limitation: the tango class(es) of the device(s) that is(are) to be created must have been registered before the server starts. If you use the high level API, the tango class(es) must be listed in the call to `run()`. If you use the lower level server API, it must be done using individual calls to `add_class()`.

6.18.1 Dynamic device from a known tango class name

If you know the tango class name but you don’t have access to the `tango.DeviceClass` (or you are too lazy to search how to get it ;-)) the way to do it is call `create_device()` / `delete_device()`. Here is an example of implementing a tango command on one of your devices that creates a device of some arbitrary class (the example assumes the tango commands ‘CreateDevice’ and ‘DeleteDevice’ receive a parameter of type `DevVarStringArray` with two strings. No error processing was done on the code for simplicity sake):

```

1  from tango import Util
2  from tango.server import Device, command
3
4  class MyDevice(Device):
5
6      @command(dtype_in=[str])
7      def CreateDevice(self, pars):
8          klass_name, dev_name = pars
9          util = Util.instance()
10         util.create_device(klass_name, dev_name, alias=None, cb=None)
11
12     @command(dtype_in=[str])
13     def DeleteDevice(self, pars):
14         klass_name, dev_name = pars
15         util = Util.instance()
16         util.delete_device(klass_name, dev_name)

```

An optional callback can be registered that will be executed after the device is registered in the tango database but before the actual device object is created and its `init_device` method is called. It can be used, for example, to initialize some device properties.

6.18.2 Dynamic device from a known tango class

If you already have access to the `DeviceClass` object that corresponds to the tango class of the device to be created you can call directly the `create_device()` / `delete_device()`. For example, if you wish to create a clone of your device, you can create a tango command called `Clone`:

```

1 class MyDevice(tango.Device):
2
3     def fill_new_device_properties(self, dev_name):
4         prop_names = db.get_device_property_list(self.get_name(), "*")
5         prop_values = db.get_device_property(self.get_name(), prop_names.value_
↳string)
6         db.put_device_property(dev_name, prop_values)
7
8         # do the same for attributes...
9         ...
10
11    def Clone(self, dev_name):
12        klass = self.get_device_class()
13        klass.create_device(dev_name, alias=None, cb=self.fill_new_device_
↳properties)
14
15    def DeleteSibling(self, dev_name):
16        klass = self.get_device_class()
17        klass.delete_device(dev_name)

```

Note that the `cb` parameter is optional. In the example it is given for demonstration purposes only.

6.19 Write a server (original API)

This chapter describes how to develop a PyTango device server using the original PyTango server API. This API mimics the C++ API and is considered low level. You should write a server using this API if you are using code generated by `Pogo` tool or if for some reason the high level API helper doesn't provide a feature you need (in that case think of writing a mail to tango mailing list explaining what you cannot do).

6.19.1 The main part of a Python device server

The rule of this part of a Tango device server is to:

- Create the `Util` object passing it the Python interpreter command line arguments
- Add to this object the list of Tango class(es) which have to be hosted by this interpreter
- Initialize the device server
- Run the device server loop

The following is a typical code for this main function:

```

1 if __name__ == '__main__':
2     util = tango.Util(sys.argv)
3     util.add_class(PyDsExpClass, PyDsExp)
4
5     U = tango.Util.instance()
6     U.server_init()
7     U.server_run()

```

Line 2 Create the `Util` object passing it the interpreter command line arguments

Line 3 Add the Tango class *PyDsExp* to the device server. The *Util.add_class()* method of the *Util* class has two arguments which are the Tango class *PyDsExpClass* instance and the Tango *PyDsExp* instance. This *Util.add_class()* method is only available since version 7.1.2. If you are using an older version please use *Util.add_TgClass()* instead.

Line 7 Initialize the Tango device server

Line 8 Run the device server loop

6.19.2 The *PyDsExpClass* class in Python

The rule of this class is to :

- Host and manage data you have only once for the Tango class whatever devices of this class will be created
- Define Tango class command(s)
- Define Tango class attribute(s)

In our example, the code of this Python class looks like:

```

1 class PyDsExpClass(tango.DeviceClass):
2
3     cmd_list = { 'IOLong' : [ [ tango.ArgType.DevLong, "Number" ],
4                             [ tango.ArgType.DevLong, "Number * 2" ] ],
5                   'IOStringArray' : [ [ tango.ArgType.DevVarStringArray, "Array of
↵string" ],
6                                       [ tango.ArgType.DevVarStringArray, "This
↵reversed array" ] ],
7               }
8
9     attr_list = { 'Long_attr' : [ [ tango.ArgType.DevLong ,
10                                  tango.AttrDataFormat.SCALAR ,
11                                  tango.AttrWriteType.READ],
12                                  { 'min alarm' : 1000, 'max alarm' : 1500 } ],
13
14                   'Short_attr_rw' : [ [ tango.ArgType.DevShort,
15                                          tango.AttrDataFormat.SCALAR,
16                                          tango.AttrWriteType.READ_WRITE ] ]
17     }

```

Line 1 The *PyDsExpClass* class has to inherit from the *DeviceClass* class

Line 3 to 7 Definition of the *cmd_list* dict defining commands. The *IOLong* command is defined at lines 3 and 4. The *IOStringArray* command is defined in lines 5 and 6

Line 9 to 17 Definition of the *attr_list* dict defining attributes. The *Long_attr* attribute is defined at lines 9 to 12 and the *Short_attr_rw* attribute is defined at lines 14 to 16

If you have something specific to do in the class constructor like initializing some specific data member, you will have to code a class constructor. An example of such a constructor is

```

1 def __init__(self, name):
2     tango.DeviceClass.__init__(self, name)
3     self.set_type("TestDevice")

```

The device type is set at line 3.

6.19.3 Defining commands

As shown in the previous example, commands have to be defined in a `dict` called `cmd_list` as a data member of the `xxxClass` class of the Tango class. This `dict` has one element per command. The element key is the command name. The element value is a python list which defines the command. The generic form of a command definition is:

```
'cmd_name' : [ [in_type, <"In desc">], [out_type, <"Out desc">],
               <{opt parameters}>]
```

The first element of the value list is itself a list with the command input data type (one of the `tango.ArgType` pseudo enumeration value) and optionally a string describing this input argument. The second element of the value list is also a list with the command output data type (one of the `tango.ArgType` pseudo enumeration value) and optionally a string describing it. These two elements are mandatory. The third list element is optional and allows additional command definition. The authorized element for this `dict` are summarized in the following array:

key	Value	Definition
"display level"	DispLevel enum value	The command display level
"polling period"	Any number	The command polling period (mS)
"default command"	True or False	To define that it is the default command

6.19.4 Defining attributes

As shown in the previous example, attributes have to be defined in a `dict` called `attr_list` as a data member of the `xxxClass` class of the Tango class. This `dict` has one element per attribute. The element key is the attribute name. The element value is a python `list` which defines the attribute. The generic form of an attribute definition is:

```
'attr_name' : [ [mandatory parameters], <{opt parameters}>]
```

For any kind of attributes, the mandatory parameters are:

```
[attr data type, attr data format, attr data R/W type]
```

The attribute data type is one of the possible value for attributes of the `tango.ArgType` pseudo enumeration. The attribute data format is one of the possible value of the `tango.AttrDataFormat` pseudo enumeration and the attribute R/W type is one of the possible value of the `tango.AttrWriteType` pseudo enumeration. For spectrum attribute, you have to add the maximum X size (a number). For image attribute, you have to add the maximum X and Y dimension (two numbers). The authorized elements for the `dict` defining optional parameters are summarized in the following array:

key	value	definition
"display level"	tango.DispLevel enum value	The attribute display level
"polling period"	Any number	The attribute polling period (mS)
"memorized"	"true" or "true_without_hard_applied"	Define if and how the att. is memorized
"label"	A string	The attribute label
"description"	A string	The attribute description
"unit"	A string	The attribute unit
"standard unit"	A number	The attribute standard unit
"display unit"	A string	The attribute display unit
"format"	A string	The attribute display format
"max value"	A number	The attribute max value
"min value"	A number	The attribute min value
"max alarm"	A number	The attribute max alarm
"min alarm"	A number	The attribute min alarm
"min warning"	A number	The attribute min warning
"max warning"	A number	The attribute max warning
"delta time"	A number	The attribute RDS alarm delta time
"delta val"	A number	The attribute RDS alarm delta val

6.19.5 The PyDsExp class in Python

The rule of this class is to implement methods executed by commands and attributes. In our example, the code of this class looks like:

```

1 class PyDsExp(tango.Device):
2
3     def __init__(self, cl, name):
4         tango.Device.__init__(self, cl, name)
5         self.info_stream('In PyDsExp.__init__')
6         PyDsExp.init_device(self)
7
8     def init_device(self):
9         self.info_stream('In Python init_device method')
10        self.set_state(tango.DevState.ON)
11        self.attr_short_rw = 66
12        self.attr_long = 1246
13
14        #-----
15
16    def delete_device(self):
17        self.info_stream('PyDsExp.delete_device')
18
19        #-----
20        # COMMANDS
21        #-----
22
23    def is_IOLong_allowed(self):
24        return self.get_state() == tango.DevState.ON
25
26    def IOLong(self, in_data):

```

(continues on next page)

(continued from previous page)

```

27     self.info_stream('IOLong', in_data)
28     in_data = in_data * 2
29     self.info_stream('IOLong returns', in_data)
30     return in_data
31
32     #-----
33
34     def is_IOStringArray_allowed(self):
35         return self.get_state() == tango.DevState.ON
36
37     def IOStringArray(self, in_data):
38         l = range(len(in_data)-1, -1, -1)
39         out_index=0
40         out_data=[]
41         for i in l:
42             self.info_stream('IOStringArray <-', in_data[out_index])
43             out_data.append(in_data[i])
44             self.info_stream('IOStringArray ->', out_data[out_index])
45             out_index += 1
46         self.y = out_data
47         return out_data
48
49     #-----
50     # ATTRIBUTES
51     #-----
52
53     def read_attr_hardware(self, data):
54         self.info_stream('In read_attr_hardware')
55
56     def read_Long_attr(self, the_att):
57         self.info_stream("read_Long_attr")
58
59         the_att.set_value(self.attr_long)
60
61     def is_Long_attr_allowed(self, req_type):
62         return self.get_state() in (tango.DevState.ON,)
63
64     def read_Short_attr_rw(self, the_att):
65         self.info_stream("read_Short_attr_rw")
66
67         the_att.set_value(self.attr_short_rw)
68
69     def write_Short_attr_rw(self, the_att):
70         self.info_stream("write_Short_attr_rw")
71
72         self.attr_short_rw = the_att.get_write_value()
73
74     def is_Short_attr_rw_allowed(self, req_type):
75         return self.get_state() in (tango.DevState.ON,)

```

Line 1 The PyDsExp class has to inherit from the tango.Device (this will used the latest device implementation class available, e.g. Device_5Impl)

Line 3 to 6 PyDsExp class constructor. Note that at line 6, it calls the *init_device()* method

Line 8 to 12 The *init_device()* method. It sets the device state (line 9) and initialises some data members

Line 16 to 17 The *delete_device()* method. This method is not mandatory. You define it only if you have to do something specific before the device is destroyed

Line 23 to 30 The two methods for the *IOLong* command. The first method is called *is_IOLong_allowed()* and it is the command *is_allowed* method (line 23 to 24). The second method has the same name than the command name. It is the method which executes the command. The command input

data type is a Tango long and therefore, this method receives a python integer.

Line 34 to 47 The two methods for the *IOStringArray* command. The first method is its `is_allowed` method (Line 34 to 35). The second one is the command execution method (Line 37 to 47). The command input data type is a string array. Therefore, the method receives the array in a python list of python strings.

Line 53 to 54 The `read_attr_hardware()` method. Its argument is a Python sequence of Python integer.

Line 56 to 59 The method executed when the *Long_attr* attribute is read. Note that before PyTango 7 it sets the attribute value with the `tango.set_attribute_value` function. Now the same can be done using the `set_value` of the attribute object

Line 61 to 62 The `is_allowed` method for the *Long_attr* attribute. This is an optional method that is called when the attribute is read or written. Not defining it has the same effect as always returning True. The parameter `req_type` is of type `AttrReqType` which tells if the method is called due to a read or write request. Since this is a read-only attribute, the method will only be called for read requests, obviously.

Line 64 to 67 The method executed when the *Short_attr_rw* attribute is read.

Line 69 to 72 The method executed when the *Short_attr_rw* attribute is written. Note that before PyTango 7 it gets the attribute value with a call to the Attribute method `get_write_value` with a list as argument. Now the write value can be obtained as the return value of the `get_write_value` call. And in case it is a scalar there is no more the need to extract it from the list.

Line 74 to 75 The `is_allowed` method for the *Short_attr_rw* attribute. This is an optional method that is called when the attribute is read or written. Not defining it has the same effect as always returning True. The parameter `req_type` is of type `AttrReqType` which tells if the method is called due to a read or write request.

General methods

The following array summarizes how the general methods we have in a Tango device server are implemented in Python.

Name	Input par (with "self")	return value	mandatory
<code>init_device</code>	None	None	Yes
<code>delete_device</code>	None	None	No
<code>always_executed_hook</code>	None	None	No
<code>signal_handler</code>	<code>int</code>	None	No
<code>read_attr_hardware</code>	<code>sequence<int></code>	None	No

Implementing a command

Commands are defined as described above. Nevertheless, some methods implementing them have to be written. These methods names are fixed and depend on command name. They have to be called:

- `is_<Cmd_name>_allowed(self)`
- `<Cmd_name>(self, arg)`

For instance, with a command called *MyCmd*, its `is_allowed` method has to be called `is_MyCmd_allowed` and its execution method has to be called simply `MyCmd`. The following array gives some more info on these methods.

Name	Input par (with "self")	return value	mandatory
<code>is_<Cmd_name>_allowed</code>	None	Python boolean	No
<code>Cmd_name</code>	Depends on cmd type	Depends on cmd type	Yes

Please check [Data types](#) chapter to understand the data types that can be used in command parameters and return values.

The following code is an example of how you write code executed when a client calls a command named IOLong:

```

1 def is_IOLong_allowed(self):
2     self.debug_stream("in is_IOLong_allowed")
3     return self.get_state() == tango.DevState.ON
4
5 def IOLong(self, in_data):
6     self.info_stream('IOLong', in_data)
7     in_data = in_data * 2
8     self.info_stream('IOLong returns', in_data)
9     return in_data

```

Line 1-3 the `is_IOLong_allowed` method determines in which conditions the command 'IOLong' can be executed. In this case, the command can only be executed if the device is in 'ON' state.

Line 6 write a log message to the tango INFO stream (click [here](#) for more information about PyTango log system).

Line 7 does something with the input parameter

Line 8 write another log message to the tango INFO stream (click [here](#) for more information about PyTango log system).

Line 9 return the output of executing the tango command

Implementing an attribute

Attributes are defined as described in chapter 5.3.2. Nevertheless, some methods implementing them have to be written. These methods names are fixed and depend on attribute name. They have to be called:

- `is_<Attr_name>_allowed(self, req_type)`
- `read_<Attr_name>(self, attr)`
- `write_<Attr_name>(self, attr)`

For instance, with an attribute called *MyAttr*, its `is_allowed` method has to be called `is_MyAttr_allowed`, its `read` method has to be called `read_MyAttr` and its `write` method has to be called `write_MyAttr`. The `attr` parameter is an instance of `Attr`. Unlike the commands, the `is_allowed` method for attributes receives a parameter of type `AttrReqtype`.

Please check [Data types](#) chapter to understand the data types that can be used in attribute.

The following code is an example of how you write code executed when a client read an attribute which is called `Long_attr`:

```

1 def read_Long_attr(self, the_attr):
2     self.info_stream("read attribute name Long_attr")
3     the_attr.set_value(self.attr_long)

```

Line 1 Method declaration with "the_attr" being an instance of the Attribute class representing the `Long_attr` attribute

Line 2 write a log message to the tango INFO stream (click [here](#) for more information about PyTango log system).

Line 3 Set the attribute value using the method `set_value()` with the attribute value as parameter.

The following code is an example of how you write code executed when a client write the `Short_attr_rw` attribute:

```
1 def write_Short_attr_rw(self, the_attr):
2     self.info_stream("In write_Short_attr_rw for attribute ", the_attr.get_name())
3     self.attr_short_rw = the_attr.get_write_value(data)
```

Line 1 Method declaration with “the_attr” being an instance of the Attribute class representing the Short_attr_rw attribute

Line 2 write a log message to the tango INFO stream (click [here](#) for more information about PyTango log system).

Line 3 Get the value sent by the client using the method get_write_value() and store the value written in the device object. Our attribute is a scalar short attribute so the return value is an int

HOW TO CONTRIBUTE

Everyone is welcome to contribute to PyTango project. If you don't feel comfortable with writing core PyTango we are looking for contributors to documentation or/and tests.

7.1 Workflow

A normal Git workflow is used. You can find how to automate your git branching workflow [example](#). Good practices:

- There is no special policy regarding commit messages. They should be short (50 chars or less) and contain summary of all changes,
- A CONTRIBUTING file is required,
- Pull requests should be ALWAYS made to develop branch, not to a master branch.

7.2 reStructuredText and Sphinx

Documentation is written in [reStructuredText](#) and built with [Sphinx](#) - it's easy to contribute. It also uses [autodoc](#) importing docstrings from tango package. Theme is not important, a theme prepared for Tango Community can be also used.

To test the docs locally requires Python ≥ 3.5 :

- `$ pip install sphinx sphinx_rtd_theme`
- `$ python setup.py build_doc`

7.3 Source code standard

All code should be [PEP8](#) compatible. We have set up checking code quality with [Codacy](#) which uses [PyLint](#) under the hood. You can see how well your code is rated on your PR's page.

Note: The accepted policy is that your code **cannot** introduce more issues than it solves!

You can also use other tools for checking [PEP8](#) compliance for your personal use. One good example of such a tool is [Flake8](#) which combines [PEP8](#) and [PyFlakes](#). There are [plugins](#) for various IDEs so that you can use your favourite tool easily.

7.4 Using Docker for development

Docker containers are useful for developing, testing and debugging PyTango. See the folder `.devcontainer` in the root of the source repo. It includes instructions for building the Docker images and using them for development.

For direct usage, rather than PyTango development, a Docker image with PyTango already installed is available: <https://hub.docker.com/r/tangocs/tango-pytango>.

7.5 Releasing a new version

From time to time a new version should be released. Anyone who wishes to see some features of the development branch released is free to make a new release. The basic steps required are as follows:

Pick a version number

- Semantic version numbering is used: `<major>.<minor>.<patch>`
- The major and minor version fields (9.3) track the TANGO C++ core version.
- Small changes are done as patch releases. For these the version number should correspond the current development number since each release process finishes with a version bump.
- **Patch release example:**
 - `9.3.2.devN` or `9.3.2aN` or `9.3.2bN` (current development branch)
 - changes to `9.3.2` (the actual release)
 - changes to `9.3.3.dev0` (bump the patch version at the end of the release process)

Create an issue in Github

- This is to inform the community that a release is planned.
- Use a checklist similar to the one below:

Task list:

- Read steps in the how-to-contribute docs for making a release
- Pull request to update changelog and bump version
- Merge PR (this is the last PR for the release)
- Merge develop into stable
- Make sure Travis and Appveyor are OK on stable branch
- Make sure the documentation is updated for stable (readthedocs)
- Create an annotated tag from stable branch
- Make sure the documentation is updated for release (readthedocs)
- Upload the new version to PyPI
- Bump the version with “-dev” in the develop branch
- Create and fill in the release description on GitHub
- Build conda packages
- Advertise the release on the mailing list
- Close this issue

- A check list in this form on github can be ticked off as the work progresses.

Make a branch from `develop` to prepare the release

- Example branch name: `prepare-v9.3.2`.

- Edit the changelog (in `docs/revision.rst`). Include *all* pull requests since the previous release.
- Bump the versions (`tango/release.py` and `appveyor.yml`). E.g. `version_info = (9, 3, 2)`, and `version: 9.3.2.{build}`
- Create a pull request to get these changes reviewed before proceeding.

Merge stable into develop

- Wait until the preparation branch pull request has been merged.
- Merge `stable` into the latest `develop`. It is recommended to do a fast-forward merge in order to avoid a confusing merge commit. This can be done by simply pushing `develop` to `stable` using this command:

```
$ git push origin develop:stable
```

This way the release tag corresponds to the actual release commit both on the `stable` and `develop` branches.

- In general, the `stable` branch should point to the latest release.

Make sure Travis and AppVeyor are OK on stable branch

- On Travis, all tests, on all versions of Python must be passing. If not, bad luck - you'll have to fix it first, and go back a few steps...
- On AppVeyor, all builds, on all versions of Python must be passing. If not, bad luck - you'll have to fix it first, and go back a few steps...

Make sure the documentation is updated

- Log in to <https://readthedocs.org>.
- Get account permissions for <https://readthedocs.org/projects/pytango> from another contributor, if necessary.
- **Readthedocs *should* automatically build the docs for each:**
 - push to `develop` (latest docs)
 - push to `stable` (stable docs)
 - new tags (e.g v9.3.2)
- ***But, the webhooks are somehow broken, so it probably won't work automatically!***
 - Trigger the builds manually here: <https://readthedocs.org/projects/pytango/builds/>
 - Set the new version to "active" here: <https://readthedocs.org/dashboard/pytango/versions/>

Create an annotated tag for the release

- Note: Github's release page makes lightweight tags which we don't want
- **Create tag:**
 - `$ git checkout stable`
 - `$ git pull`
 - `$ git tag -a -m "tag v9.3.2" v9.3.2`
 - `$ git push -v origin refs/tags/v9.3.2`

Upload the new version to PyPI

- Log in to <https://pypi.org>.
- Get account permissions for PyTango from another contributor, if necessary.

- If necessary, pip install twine: <https://pypi.org/project/twine/>)
- **Build release from the tagged commit:**
 - \$ git clean -xfd # Warning - remove all non-versioned files and directories
 - \$ git fetch
 - \$ git checkout v9.3.2
 - \$ python setup.py sdist
- **Optional: Upload to <https://test.pypi.org>, and make sure all is well:**
 - \$ twine upload -r testpypi dist/pytango-9.3.2.tar.gz
- **Optional: Test installation (in a virtualenv):**
 - \$ pip install -i <https://test.pypi.org/simple/> pytango
- **Upload the source tarball to the real PyPI:**
 - \$ twine upload dist/pytango-9.3.2.tar.gz
- **Run build for the tag on AppVeyor, download artifacts, and upload wheels:**
 - \$ twine upload dist/pytango-9.3.2-cp27-cp27m-win32.whl
 - \$ twine upload dist/pytango-9.3.2-cp27-cp27m-win_amd64.whl
 - \$ twine upload dist/pytango-9.3.2-cp36-cp36m-win32.whl
 - \$ twine upload dist/pytango-9.3.2-cp36-cp36m-win_amd64.whl
 - \$ twine upload dist/pytango-9.3.2-cp37-cp37m-win32.whl
 - \$ twine upload dist/pytango-9.3.2-cp37-cp37m-win_amd64.whl

Bump the version with “-dev” in the develop branch

- Make branch like bump-v9.3.2.dev.0 from head of develop.
- Change all references to next version. E.g. if releasing v9.3.2, then update references to v9.3.3.
- This includes files like README.rst, doc/howto.rst, doc/start.rst.
- In tango/release.py, change version_info, e.g. from (9, 3, 2) to (9, 3, 3, 'dev', 0).
- In appveyor.yml, change version, e.g. from 9.3.2.{build} to 9.3.3.dev0.{build}.
- Create PR, merge to develop.

Create and fill in the release description on GitHub

- Go to the Tags page: <https://github.com/tango-controls/pytango/tags>
- Find the tag created above and click “Create release”.
- Content must be the same as the details in the changelog. List all the pull requests since the previous version.

Build conda packages

- This is tricky, so ask a contributor from the ESRF to do it.

Advertise the release on the mailing list

- Post on the Python development list.
- Example of a previous post: <http://www.tango-controls.org/community/forum/c/development/python/pytango-921-release/>

Close off release issue

- All the items on the check list should be ticked off by now.
- Close the issue.

Answers to general Tango questions can be found in the [general tango tutorial](#).

Please also check the [general tango how to](#).

How can I report an issue?

Bug reports are very valuable for the community.

Please open a new issue on the GitHub [issues](#) page.

How can I contribute to PyTango and the documentation?

Contribution are always welcome!

You can open pull requests on the GitHub [PRs](#) page.

I got a libboost_python error when I try to import tango module...

For instance:

```
>>> import tango
ImportError: libboost_python.so.1.53.0: cannot open shared object file: No such
↪file or directory
```

You must check that you have the correct boost python installed on your computer. To see which boost python file PyTango needs, type:

```
$ ldd /usr/lib64/python2.7/site-packages/tango/_tango.so
linux-vdso.so.1 => (0x00007ffea7562000)
libtango.so.9 => /lib64/libtango.so.9 (0x00007fac04011000)
libomniORB4.so.1 => /lib64/libomniORB4.so.1 (0x00007fac03c62000)
libboost_python.so.1.53.0 => not found
[...]
```

I have more questions, where can I ask?

The [Tango forum](#) is a good place to get some support. Meet us in the [Python section](#).

PYTANGO ENHANCEMENT PROPOSALS

9.1 TEP 1 - Device Server High Level API

TEP:	1
Title:	Device Server High Level API
Version:	2.2.0
Last-Modified:	10-Sep-2014
Author:	Tiago Coutinho <tcoutinho@cells.es>
Status:	Active
Type:	Standards Track
Content-Type:	text/x-rst
Created:	17-Oct-2012

9.1.1 Abstract

This TEP aims to define a new high level API for writing device servers.

9.1.2 Rationale

The code for Tango device servers written in Python often obey a pattern. It would be nice if non tango experts could create tango device servers without having to code some obscure tango related code. It would also be nice if the tango programming interface would be more pythonic. The final goal is to make writing tango device servers as easy as:

```
class Motor(Device):
    __metaclass__ = DeviceMeta

    position = attribute()

    def read_position(self):
        return 2.3

    @command()
    def move(self, position):
        pass

if __name__ == "__main__":
    server_run((Motor,))
```

9.1.3 Places to simplify

After looking at most python device servers one can see some patterns:

At <Device> class level:

1. <Device> always inherits from latest available DeviceImpl from pogo version
2. **constructor always does the same:**
 1. calls super constructor
 2. debug message
 3. calls `init_device`
3. all methods have `debug_stream` as first instruction
4. `init_device` does additionally `get_device_properties()`
5. *read attribute* methods follow the pattern:

```
def read_Attr(self, attr):
    self.debug_stream()
    value = get_value_from_hardware()
    attr.set_value(value)
```

6. *write attribute* methods follow the pattern:

```
def write_Attr(self, attr):
    self.debug_stream()
    w_value = attr.get_write_value()
    apply_value_to_hardware(w_value)
```

At <Device>Class class level:

1. A <Device>Class class exists for every <DeviceName> class
2. The <Device>Class class only contains attributes, commands and properties descriptions (no logic)
3. The `attr_list` description always follows the same (non explicit) pattern (and so does `cmd_list`, `class_property_list`, `device_property_list`)
4. the syntax for `attr_list`, `cmd_list`, etc is far from understandable

At *main()* level:

1. **The `main()` method always does the same:**
 1. create *Util*
 2. register tango class
 3. when registering a python class to become a tango class, 99.9% of times the python class name is the same as the tango class name (example: Motor is registered as tango class "Motor")
 4. call `server_init()`
 5. call `server_run()`

9.1.4 High level API

The goals of the high level API are:

Maintain all features of low-level API available from high-level API

Everything that was done with the low-level API must also be possible to do with the new API.

All tango features should be available by direct usage of the new simplified, cleaner high-level API and through direct access to the low-level API.

Automatic inheritance from the latest** DeviceImpl

Currently Devices need to inherit from a direct Tango device implementation (`DeviceImpl`, or `Device_2Impl`, `Device_3Impl`, `Device_4Impl`, etc) according to the tango version being used during the development.

In order to keep the code up to date with tango, every time a new Tango IDL is released, the code of **every** device server needs to be manually updated to inherit from the newest tango version.

By inheriting from a new high-level `Device` (which itself automatically *decides* from which `DeviceImpl` version it should inherit), the device servers are always up to date with the latest tango release without need for manual intervention (see [tango.server](#)).

Low-level way:

```
class Motor(PyTango.Device_4Impl):
    pass
```

High-level way:

```
class Motor(PyTango.server.Device):
    pass
```

Default implementation of Device constructor

99% of the different device classes which inherit from low level `DeviceImpl` only implement `__init__` to call their `init_device` (see [tango.server](#)).

`Device` already calls `init_device`.

Low-level way:

```
class Motor(PyTango.Device_4Impl):

    def __init__(self, dev_class, name):
        PyTango.Device_4Impl.__init__(self, dev_class, name)
        self.init_device()
```

High-level way:

```
class Motor(PyTango.server.Device):

    # Nothing to be done!

    pass
```

Default implementation of `init_device()`

99% of different device classes which inherit from low level `DeviceImpl` have an implementation of `init_device` which *at least* calls `get_device_properties()` (see `tango.server`).

`init_device()` already calls `get_device_properties()`.

Low-level way:

```
class Motor(PyTango.Device_4Impl):  
  
    def init_device(self):  
        self.get_device_properties()
```

High-level way:

```
class Motor(PyTango.server.Device):  
    # Nothing to be done!  
    pass
```

Remove the need to code `DeviceClass`

99% of different device servers only need to implement their own subclass of `DeviceClass` to register the attribute, commands, device and class properties by using the corresponding `attr_list`, `cmd_list`, `device_property_list` and `class_property_list`.

With the high-level API we completely remove the need to code the `DeviceClass` by registering attribute, commands, device and class properties in the `Device` with a more pythonic API (see `tango.server`)

1. Hide `<Device>Class` class completely
2. simplify `main()`

Low-level way:

```
class Motor(PyTango.Device_4Impl):  
  
    def read_Position(self, attr):  
        pass  
  
class MotorClass(PyTango.DeviceClass):  
  
    class_property_list = { }  
    device_property_list = { }  
    cmd_list = { }  
  
    attr_list = {  
        'Position':  
            [[PyTango.DevDouble,  
             PyTango.SCALAR,  
             PyTango.READ]],  
    }  
  
    def __init__(self, name):  
        PyTango.DeviceClass.__init__(self, name)  
        self.set_type(name)
```

High-level way:

```
class Motor(PyTango.server.Device):
```

(continues on next page)

(continued from previous page)

```

position = PyTango.server.attribute(dtype=float, )

def read_position(self):
    pass

```

Pythonic read/write attribute

With the low level API, it feels strange for a non tango programmer to have to write:

```

def read_Position(self, attr):
    # ...
    attr.set_value(new_position)

def read_Position(self, attr):
    # ...
    attr.set_value_date_quality(new_position, time.time(), AttrQuality.CHANGING)

```

A more pythonic way would be:

```

def read_position(self):
    # ...
    self.position = new_position

def read_position(self):
    # ...
    self.position = new_position, time.time(), AttrQuality.CHANGING

```

Or even:

```

def read_position(self):
    # ...
    return new_position

def read_position(self):
    # ...
    return new_position, time.time(), AttrQuality.CHANGING

```

Simplify *main()*

the typical *main()* method could be greatly simplified. initializing tango, registering tango classes, initializing and running the server loop and managing errors could all be done with the single function call to `server_run()`

Low-level way:

```

def main():
    try:
        py = PyTango.Util(sys.argv)
        py.add_class(MotorClass, Motor, 'Motor')

        U = PyTango.Util.instance()
        U.server_init()
        U.server_run()

    except PyTango.DevFailed, e:
        print '-----> Received a DevFailed exception:', e
    except Exception, e:
        print '-----> An unforeseen exception occured...', e

```

High-level way:

```
def main():
    classes = Motor,
    PyTango.server_run(classes)
```

9.1.5 In practice

Currently, a pogo generated device server code for a Motor having a double attribute *position* would look like this:

```
#!/usr/bin/env python
# -*- coding:utf-8 -*-

#####
## license :
##-----
##
## File :      Motor.py
##
## Project :
##
## $Author :   t$
##
## $Revision : $
##
## $Date :     $
##
## $HeadUrl :  $
##-----
##          This file is generated by POGO
##    (Program Obviously used to Generate tango Object)
##
##          (c) - Software Engineering Group - ESRF
#####

"""

__all__ = ["Motor", "MotorClass", "main"]

__docformat__ = 'restructuredtext'

import PyTango
import sys
# Add additional import
#----- PROTECTED REGION ID(Motor.additionnal_import) ENABLED START -----#

#----- PROTECTED REGION END -----# //      Motor.additionnal_import

#####
## Device States Description
##
## No states for this device
#####

class Motor (PyTango.Device_4Impl):

#----- Add you global variables here -----
#----- PROTECTED REGION ID(Motor.global_variables) ENABLED START -----#
```

(continues on next page)

(continued from previous page)

```

#----- PROTECTED REGION END -----# //      Motor.global_variables
#-----
#      Device constructor
#-----
def __init__(self,cl, name):
    PyTango.Device_4Impl.__init__(self,cl,name)
    self.debug_stream("In " + self.get_name() + ".__init__()")
    Motor.init_device(self)

#-----
#      Device destructor
#-----
def delete_device(self):
    self.debug_stream("In " + self.get_name() + ".delete_device()")
    #----- PROTECTED REGION ID(Motor.delete_device) ENABLED START -----#

    #----- PROTECTED REGION END -----# //      Motor.delete_device

#-----
#      Device initialization
#-----
def init_device(self):
    self.debug_stream("In " + self.get_name() + ".init_device()")
    self.get_device_properties(self.get_device_class())
    self.attr_Position_read = 0.0
    #----- PROTECTED REGION ID(Motor.init_device) ENABLED START -----#

    #----- PROTECTED REGION END -----# //      Motor.init_device

#-----
#      Always excuted hook method
#-----
def always_executed_hook(self):
    self.debug_stream("In " + self.get_name() + ".always_excuted_hook()")
    #----- PROTECTED REGION ID(Motor.always_executed_hook) ENABLED START -----#

    #----- PROTECTED REGION END -----# //      Motor.always_executed_hook

#=====
#
#      Motor read/write attribute methods
#
#=====

#-----
#      Read Position attribute
#-----
def read_Position(self, attr):
    self.debug_stream("In " + self.get_name() + ".read_Position()")
    #----- PROTECTED REGION ID(Motor.Position_read) ENABLED START -----#
    self.attr_Position_read = 1.0
    #----- PROTECTED REGION END -----# //      Motor.Position_read
    attr.set_value(self.attr_Position_read)

#-----
#      Read Attribute Hardware
#-----
def read_attr_hardware(self, data):
    self.debug_stream("In " + self.get_name() + ".read_attr_hardware()")
    #----- PROTECTED REGION ID(Motor.read_attr_hardware) ENABLED START -----#

```

(continues on next page)

(continued from previous page)

```

#----- PROTECTED REGION END -----# //      Motor.read_attr_hardware

#-----
#
#      Motor command methods
#
#-----

#-----
#
#      MotorClass class definition
#
#-----
class MotorClass(PyTango.DeviceClass):

    #      Class Properties
    class_property_list = {
        }

    #      Device Properties
    device_property_list = {
        }

    #      Command definitions
    cmd_list = {
        }

    #      Attribute definitions
    attr_list = {
        'Position':
            [[PyTango.DevDouble,
              PyTango.SCALAR,
              PyTango.READ]],
        }

#-----
#      MotorClass Constructor
#-----
def __init__(self, name):
    PyTango.DeviceClass.__init__(self, name)
    self.set_type(name);
    print "In Motor Class constructor"

#-----
#
#      Motor class main method
#
#-----
def main():
    try:
        py = PyTango.Util(sys.argv)
        py.add_class(MotorClass, Motor, 'Motor')

        U = PyTango.Util.instance()
        U.server_init()

```

(continues on next page)

(continued from previous page)

```

        U.server_run()

    except PyTango.DevFailed,e:
        print '-----> Received a DevFailed exception:',e
    except Exception,e:
        print '-----> An unforeseen exception occured....',e

if __name__ == '__main__':
    main()

```

To make things more fair, let's analyse the stripped version of the code instead:

```

import PyTango
import sys

class Motor (PyTango.Device_4Impl):

    def __init__(self,cl, name):
        PyTango.Device_4Impl.__init__(self,cl,name)
        self.debug_stream("In " + self.get_name() + ".__init__()")
        Motor.init_device(self)

    def delete_device(self):
        self.debug_stream("In " + self.get_name() + ".delete_device()")

    def init_device(self):
        self.debug_stream("In " + self.get_name() + ".init_device()")
        self.get_device_properties(self.get_device_class())
        self.attr_Position_read = 0.0

    def always_executed_hook(self):
        self.debug_stream("In " + self.get_name() + ".always_excuted_hook()")

    def read_Position(self, attr):
        self.debug_stream("In " + self.get_name() + ".read_Position()")
        self.attr_Position_read = 1.0
        attr.set_value(self.attr_Position_read)

    def read_attr_hardware(self, data):
        self.debug_stream("In " + self.get_name() + ".read_attr_hardware()")

class MotorClass(PyTango.DeviceClass):

    class_property_list = {
    }

    device_property_list = {
    }

    cmd_list = {
    }

    attr_list = {
        'Position':
            [[PyTango.DevDouble,
             PyTango.SCALAR,
             PyTango.READ]],

```

(continues on next page)

(continued from previous page)

```

    }

    def __init__(self, name):
        PyTango.DeviceClass.__init__(self, name)
        self.set_type(name);
        print "In Motor Class constructor"

def main():
    try:
        py = PyTango.Util(sys.argv)
        py.add_class(MotorClass, Motor, 'Motor')

        U = PyTango.Util.instance()
        U.server_init()
        U.server_run()

    except PyTango.DevFailed,e:
        print '-----> Received a DevFailed exception:',e
    except Exception,e:
        print '-----> An unforeseen exception occured...',e

if __name__ == '__main__':
    main()

```

And the equivalent HLAPI version of the code would be:

```

#!/usr/bin/env python

from PyTango import DebugIt, server_run
from PyTango.server import Device, DeviceMeta, attribute

class Motor(Device):
    __metaclass__ = DeviceMeta

    position = attribute()

    @DebugIt()
    def read_position(self):
        return 1.0

def main():
    server_run((Motor,))

if __name__ == "__main__":
    main()

```


9.1.6 References

tango.server

9.1.7 Changes

from 2.1.0 to 2.2.0

Changed module name from *hlapi* to *server*

from 2.0.0 to 2.1.0

Changed module name from *api2* to *hlapi* (High Level API)

From 1.0.0 to 2.0.0

- **API Changes**
 - changed Attr to attribute
 - changed Cmd to command
 - changed Prop to device_property
 - changed ClassProp to class_property
- Included command and properties in the example
- Added references to API documentation

9.1.8 Copyright

This document has been placed in the public domain.

9.2 TEP 2 - Tango database serverless

TEP:	2
Title:	Tango database serverless
Version:	1.0.0
Last-Modified:	17-Oct-2012
Author:	Tiago Coutinho < tcoutinho@cells.es >
Status:	Active
Type:	Standards Track
Content-Type:	text/x-rst
Created:	17-Oct-2012
Post-History:	17-Oct-2012

9.2.1 Abstract

This TEP aims to define a python DataBases which doesn't need a database server behind. It would make tango easier to try out by anyone and it could greatly simplify tango installation on small environments (like small, independent laboratories).

9.2.2 Motivation

I was given a openSUSE laptop so that I could do the presentation for the tango meeting held in FRMII on October 2012. Since I planned to do a demonstration as part of the presentation I installed all mysql libraries, omniorb, tango and pytango on this laptop.

During the flight to Munich I realized tango was not working because of a strange mysql server configuration done by the openSUSE distribution. I am not a mysql expert and I couldn't google for a solution. Also it made me angry to have to install all the mysql crap (libmysqlclient, mysqld, mysql-administrator, bla, bla) just to have a demo running.

At the time of writing the first version of this TEP I still didn't solve the problem! Shame on me!

Also at the same tango meeting during the tango archiving discussions I heard fake whispers or changing the tango archiving from MySQL/Oracle to NoSQL.

I started thinking if it could be possible to have an alternative implementation of DataBases without the need for a mysql server.

9.2.3 Requisites

- no dependencies on external packages
- no need for a separate database server process (at least, by default)
- no need to execute post install scripts to fill database

9.2.4 Step 1 - Gather database information

It turns out that python has a Database API specification ([PEP 249](#)). Python distribution comes natively (≥ 2.6) with not one but several persistency options ([Data Persistence](#)):

module	Native	Platforms	API	Database	Description
Native python 2.x					
<code>pickle</code>	Yes	all	dump/load	file	python serialization/marshalling module
<code>shelve</code>	Yes	all	dict	file	high level persistent, dictionary-like object
<code>marshal</code>	Yes	all	dump/load	file	Internal Python object serialization
<code>anydbm</code>	Yes	all	dict	file	Generic access to DBM-style databases. Wrapper for <code>dbhash</code> , <code>gdbm</code> , <code>dbm</code> or <code>dumbdbm</code>
<code>dbm</code>	Yes	all	dict	file	Simple "database" interface
<code>gdbm</code>	Yes	unix	dict	file	GNU's reinterpretation of <code>dbm</code>
<code>dbhash</code>	Yes	unix?	dict	file	DBM-style interface to the BSD database library (needs <code>bsddb</code>). Removed in python 3
<code>bsddb</code>	Yes	unix?	dict	file	Interface to Berkeley DB library. Removed in python 3
<code>dumbdbm</code>	Yes	all	dict	file	Portable DBM implementation
<code>sqlite3</code>	Yes	all	DBAPI2	file, memory	DB-API 2.0 interface for SQLite databases
Native Python 3.x					
<code>pickle</code>	Yes	all	dump/load	file	python serialization/marshalling module
<code>shelve</code>	Yes	all	dict	file	high level persistent, dictionary-like object
<code>marshal</code>	Yes	all	dump/load	file	Internal Python object serialization
<code>dbm</code>	Yes	all	dict	file	Interfaces to Unix "databases". Wrapper for <code>dbm.gnu</code> , <code>dbm.ndbm</code> , <code>dbm.dumb</code>
<code>dbm.gnu</code>	Yes	unix	dict	file	GNU's reinterpretation of <code>dbm</code>
<code>dbm.ndbm</code>	Yes	unix	dict	file	Interface based on <code>ndbm</code>
<code>dbm.dumb</code>	Yes	all	dict	file	Portable DBM implementation
<code>sqlite3</code>	Yes	all	DBAPI2	file, memory	DB-API 2.0 interface for SQLite databases

third-party DBAPI2

- `pyodbc`
- `mxODBC`
- `kinterbasdb`
- `mxODBC Connect`
- `MySQLdb`
- `psycopg`
- `pyPgSQL`
- `PySQLite`
- `adodbapi`
- `pymssql`
- `sapdbapi`
- `ibm_db`
- `InformixDB`

third-party NOSQL

(these may or not have python DBAPI2 interface)

- `CouchDB` - `couchdb.client`
- `MongoDB` - `pymongo` - NoSQL database
- `Cassandra` - `pycassa`

third-party database abstraction layer

- [SQLAlchemy](#) - sqlalchemy - Python SQL toolkit and Object Relational Mapper

9.2.5 Step 2 - Which module to use?

hrrrr... wrong question!

The first decision I thought it should made is which python module better suites the needs of this TEP. Then I realized I would fall into the same trap as the C++ DataBases: hard link the server to a specific database implementation (in their case MySQL).

I took a closer look at the tables above and I noticed that python persistent modules come in two flavors: dict and DBAPI2. So naturally the decision I thought it had to be made was: *which flavor to use?*

But then I realized both flavors could be used if we properly design the python DataBases.


9.2.6 Step 3 - Architecture

If you step back for a moment and look at the big picture you will see that what we need is really just a mapping between the Tango DataBase set of attributes and commands (I will call this *Tango Device DataBase API*) and the python database API oriented to tango (I will call this TDB interface).

The TDB interface should be represented by the ITangoDB. Concrete databases should implement this interface (example, DBAPI2 interface should be represented by a class TangoDBAPI2 implementing ITangoDB).

Connection to a concrete ITangoDB should be done through a factory: TangoDBFactory

The Tango DataBase device should have no logic. Through basic configuration it should be able to ask the TangoDBFactory for a concrete ITangoDB. The code of every command and attribute should be simple forward to the ITangoDB object (a part of some parameter translation and error handling).



9.2.7 Step 4 - The python DataBases

If we can make a python device server which has the same set of attributes and commands has the existing C++ DataBase (and of course the same semantic behavior), the tango DS and tango clients will never know the difference (BTW, that's one of the beauties of tango).

The C++ DataBase consists of around 80 commands and 1 mandatory attribute (the others are used for profiling) so making a python Tango DataBase device from scratch is out of the question.

Fortunately, C++ DataBase is one of the few device servers that were developed since the beginning with pogo and were successfully adapted to pogo 8. This means there is a precious `DataBase.xmi` available which can be loaded to pogo and saved as a python version. The result of doing this can be found here [here](#) (this file was generated with a beta version of the pogo 8.1 python code generator so it may contain errors).

9.2.8 Step 5 - Default database implementation

The decision to which database implementation should be used should obey the following rules:

1. should not require an extra database server process
2. should be a native python module
3. should implement python DBAPI2

It came to my attention the `sqlite3` module would be perfect as a default database implementation. This module comes with python since version 2.5 and is available in all platforms. It implements the DBAPI2 interface and can store persistently in a common OS file or even in memory.

There are many free scripts on the web to translate a mysql database to sqlite3 so one can use an existing mysql tango database and directly use it with the python DataBases with sqlite3 implementation.

9.2.9 Development

The development is being done in PyTango SVN trunk in the `tango.databases` module.

You can checkout with:

```
$ svn co https://tango-cs.svn.sourceforge.net/svnroot/tango-cs/bindings/PyTango/
↪trunk PyTango-trunk
```

9.2.10 Disadvantages

A serverless, file based, database has some disadvantages when compared to the mysql solution:

- Not possible to distribute load between Tango DataBase DS and database server (example: run the Tango DS in one machine and the database server in another)
- Not possible to have two Tango DataBase DS pointing to the same database
- Harder to upgrade to newer version of sql tables (specially if using dict based database)

Bare in mind the purpose of this TED is to simplify the process of trying tango and to ease installation and configuration on small environments (like small, independent laboratories).

9.2.11 References

- <http://wiki.python.org/moin/DbApiCheatSheet>
- <http://wiki.python.org/moin/DbApiModuleComparison>
- <http://wiki.python.org/moin/DatabaseProgramming>
- <http://wiki.python.org/moin/DbApiFaq>
- **PEP 249**
- <http://wiki.python.org/moin/ExtendingTheDbApi>
- <http://wiki.python.org/moin/DbApi3>

HISTORY OF CHANGES

Contributers T. Coutinho

Last Update Apr 30, 2020

10.1 Document revisions

Date	Revision	Description	Author
18/07/03	1.0	Initial Version	M. Ounsy
06/10/03	2.0	Extension of the "Getting Started" paragraph	A. Buteau/M. Ounsy
14/10/03	3.0	Added Exception Handling paragraph	M. Ounsy
13/06/05	4.0	Ported to Latex, added events, AttributeProxy and ApiUtil	V. Forchì
13/06/05	4.1	fixed bug with python 2.5 and and state events new Database constructor	V. Forchì
15/01/06	5.0	Added Device Server classes	E.Taurel
15/03/07	6.0	Added AttrInfoEx, AttributeConfig events, 64bits, write_attribute	T. Coutinho
21/03/07	6.1	Added groups	T. Coutinho
15/06/07	6.2	Added dynamic attributes doc	E. Taurel
06/05/08	7.0	Update to Tango 6.1. Added DB methods, version info	T. Coutinho
10/07/09	8.0	Update to Tango 7. Major refactoring. Migrated doc	T. Coutinho/R. St
24/07/09	8.1	Added migration info, added missing API doc	T. Coutinho/R. St
21/09/09	8.2	Added migration info, release of 7.0.0beta2	T. Coutinho/R. St
12/11/09	8.3	Update to Tango 7.1.	T. Coutinho/R. St
??/12/09	8.4	Update to PyTango 7.1.0 rc1	T. Coutinho/R. St
19/02/10	8.5	Update to PyTango 7.1.1	T. Coutinho/R. St
06/08/10	8.6	Update to PyTango 7.1.2	T. Coutinho
05/11/10	8.7	Update to PyTango 7.1.3	T. Coutinho
08/04/11	8.8	Update to PyTango 7.1.4	T. Coutinho
13/04/11	8.9	Update to PyTango 7.1.5	T. Coutinho
14/04/11	8.10	Update to PyTango 7.1.6	T. Coutinho
15/04/11	8.11	Update to PyTango 7.2.0	T. Coutinho
12/12/11	8.12	Update to PyTango 7.2.2	T. Coutinho
24/04/12	8.13	Update to PyTango 7.2.3	T. Coutinho
21/09/12	8.14	Update to PyTango 8.0.0	T. Coutinho
10/10/12	8.15	Update to PyTango 8.0.2	T. Coutinho
20/05/13	8.16	Update to PyTango 8.0.3	T. Coutinho
28/08/13	8.13	Update to PyTango 7.2.4	T. Coutinho
27/11/13	8.18	Update to PyTango 8.1.1	T. Coutinho
16/05/14	8.19	Update to PyTango 8.1.2	T. Coutinho
30/09/14	8.20	Update to PyTango 8.1.4	T. Coutinho
01/10/14	8.21	Update to PyTango 8.1.5	T. Coutinho
05/02/15	8.22	Update to PyTango 8.1.6	T. Coutinho
03/02/16	8.23	Update to PyTango 8.1.8	T. Coutinho

continues o

Table 1 – continued from previous page

Date	Revision	Description	Author
12/08/16	8.24	Update to PyTango 8.1.9	V. Michel
26/02/16	9.2.0a	Update to PyTango 9.2.0a	T. Coutinho
15/08/16	9.2.0	9.2.0 Release	V. Michel
23/01/17	9.2.1	9.2.1 Release	V. Michel
27/09/17	9.2.2	9.2.2 Release	G. Cuni/V. Michel
30/05/18	9.2.3	9.2.3 Release	V. Michel
30/07/18	9.2.4	9.2.4 Release	V. Michel
28/11/18	9.2.5	9.2.5 Release	A. Joubert
13/03/19	9.3.0	9.3.0 Release	T. Coutinho
08/08/19	9.3.1	9.3.1 Release	A. Joubert
30/04/19	9.3.2	9.3.2 Release	A. Joubert

10.2 Version history

Version	Changes
9.3.2	<p>9.3.2 release.</p> <p>Features:</p> <ul style="list-style-type: none"> • Pull Request #314: Add MultiDeviceTestContext for testing more than one Device • Pull Request #317: Add get_device_attribute_list and missing pipe methods to Database interface (#313) • Pull Request #327: Add EnsureOmniThread and is_omni_thread (#307, #292) <p>Changes:</p> <ul style="list-style-type: none"> • Pull Request #316: Reduce six requirement from 1.12 to 1.10 (#296) • Pull Request #326: Add Docker development container • Pull Request #330: Add enum34 to Python 2.7 docker images • Pull Request #329: Add test to verify get_device_properties called on init • Pull Request #341: Build DevFailed origin from format_exception (#340) <p>Bug/doc fixes:</p> <ul style="list-style-type: none"> • Pull Request #301: Fix documentation error • Pull Request #334: Update green mode docs and asyncio example (#333) • Pull Request #335: Generalise search for libboost_python on POSIX (#300, #310) • Pull Request #343: Extend the info on dependencies in README • Pull Request #345: Fix power_supply client example PowerOn -> TurnOn • Pull Request #347: Fix memory leak for DevEncoded attributes • Pull Request #348: Fix dynamic enum attributes created without labels (#56)

continues on next page

Table 2 – continued from previous page

Version	Changes
9.3.1	<p>9.3.1 release.</p> <p>Changes:</p> <ul style="list-style-type: none"> • Pull Request #277: Windows builds using AppVeyor (#176) • Pull Request #290: Update docs: int types maps to DevLong64 (#282) • Pull Request #293: Update exception types in proxy docstrings <p>Bug fixes:</p> <ul style="list-style-type: none"> • Pull Request #270: Add six >= 1.12 requirement (#269) • Pull Request #273: DeviceAttribute.is_empty not working correctly with latest cpp tango version (#271) • Pull Request #274: Add unit tests for spectrum attributes, including empty (#271) • Pull Request #281: Fix DevEncoded commands on Python 3 (#280) • Pull Request #288: Make sure we only convert to string python unicode/str/bytes objects (#285) • Pull Request #289: Fix compilation warnings and conda build (#286)

continues on next page

Table 2 – continued from previous page

Version	Changes
9.3.0	<p data-bbox="810 259 959 288">9.3.0 release.</p> <p data-bbox="810 293 927 322">Changes:</p> <ul data-bbox="919 338 1390 524" style="list-style-type: none"> <li data-bbox="919 338 1390 405">• Pull Request #242: Improve Python version check for enum34 install <li data-bbox="919 416 1334 450">• Pull Request #250: Develop 9.3.0 <li data-bbox="919 461 1390 524">• Pull Request #258: Change Travis CI builds to xenial <p data-bbox="810 546 932 575">Bug fixes:</p> <ul data-bbox="919 591 1390 1211" style="list-style-type: none"> <li data-bbox="919 591 1390 658">• Pull Request #245: Change for collections abstract base class <li data-bbox="919 669 1390 736">• Pull Request #247: Use IP address instead of hostname (fix #246) <li data-bbox="919 748 1390 815">• Pull Request #252: Fix wrong link to tango dependency (#235) <li data-bbox="919 826 1390 893">• Pull Request #254: Fix mapping of AttrWriteType WT_UNKNOWN <li data-bbox="919 904 1390 972">• Pull Request #257: Fix some docs and docstrings <li data-bbox="919 983 1390 1050">• Pull Request #260: add ApiUtil.cleanup() <li data-bbox="919 1061 1390 1128">• Pull Request #262: Fix compile error under Linux <li data-bbox="919 1140 1390 1211">• Pull Request #263: Fix #251: Python 2 vs Python 3: DevString with bytes

continues on next page

Table 2 – continued from previous page

Version	Changes
9.2.5	<p>9.2.5 release.</p> <p>Changes:</p> <ul style="list-style-type: none"> • Pull Request #212: Skip databaseds backends in PyTango compatibility module • Pull Request #221: DevEnum attributes can now be directly assigned labels • Pull Request #236: Cleanup db_access module • Pull Request #237: Add info about how to release a new version <p>Bug fixes:</p> <ul style="list-style-type: none"> • Pull Request #209 (issue #207): Fix documentation warnings • Pull Request #211: Yet another fix to the gevent threadpool error wrapping • Pull Request #214 (issue #213): DevEncoded attribute should produce a bytes object in python 3 • Pull Request #219: Fixing icons in documentation • Pull Request #220: Fix 'DevFailed' object does not support indexing • Pull Request #225 (issue #215): Fix exception propagation in python 3 • Pull Request #226 (issue #216): Add missing converter from python bytes to char* • Pull Request #227: Gevent issue #1260 should be fixed by now • Pull Request #232: use special case-insensitive weak values dictionary for Tango nodes

continues on next page

Table 2 – continued from previous page

Version	Changes
9.2.4	9.2.4 release. Changes: <ul style="list-style-type: none"> • Pull Request #194 (issue #188): Easier access to DevEnum attribute using python enum • Pull Request #199 (issue #195): Support python enum as dtype argument for attributes • Pull Request #205 (issue #202): Python 3.7 compatibility Bug fixes: <ul style="list-style-type: none"> • Pull Request #193 (issue #192): Fix a gevent green mode memory leak introduced in v9.2.3
9.2.3	9.2.3 release. Changes: <ul style="list-style-type: none"> • Pull Request #169: Use tango-controls theme for the documentation • Pull Request #170 (issue #171): Use a private gevent ThreadPool • Pull Request #180: Use same default encoding for python2 and python3 (utf-8) Bug fixes: <ul style="list-style-type: none"> • Pull Request #178 (issue #177): Make CmdDoneEvent.argout writable • Pull Request #178: Add GIL control for ApiUtil.get_asynch_replies • Pull Request #187 (issue #186): Fix and extend client green mode

continues on next page

Table 2 – continued from previous page

Version	Changes
9.2.2	<p>9.2.2 release.</p> <p>Features:</p> <ul style="list-style-type: none"> • Pull Request #104: Pipe Events • Pull Request #106: Implement pipe write (client and server, issue #9) • Pull Request #122: Dynamic commands • Pull Request #124: Add forward attribute • Pull Request #129: Implement mandatory property (issue #30) <p>Changes:</p> <ul style="list-style-type: none"> • Pull Request #109: Device Interface Change Events • Pull Request #113: Adding asyncio green mode documentation and a how-to on contributing • Pull Request #114: Added PEP8-ified files in tango module. • Pull Request #115: Commands polling tests (client and server) • Pull Request #116: Attribute polling tests (client and server) • Pull Request #117: Use official tango-controls conda channel • Pull Request #125: Forward attribute example • Pull Request #134: Linting pytango (with pylint + flake8) • Pull Request #137: Codacy badge in README and code quality policy in How to Contribute • Pull Request #143: Added missing PipeEventData & DevIntrChangeEventData <p>Bug fixes:</p> <ul style="list-style-type: none"> • Pull Request #85 (issue #84): Fix Gevent ThreadPool exceptions • Pull Request #94 (issue #93): Fix issues in setup file (GCC-7 build) • Pull Request #96: Filter badges from the long description • Pull Request #97: Fix/linker options • Pull Request #98: Refactor green mode for client and server APIs • Pull Request #101 (issue #100) check for None and return null string
258	<p>Chapter 10. History of changes</p> <ul style="list-style-type: none"> • Pull Request #102: Update server tests • Pull Request #103: Cache build ob-

Table 2 – continued from previous page

Version	Changes
9.2.1	<p data-bbox="810 262 959 286">9.2.1 release.</p> <p data-bbox="810 293 922 318">Features:</p> <ul data-bbox="919 338 1385 432" style="list-style-type: none"> <li data-bbox="919 338 1385 432">• Pull Requests #70: Add test_context and test_utils modules, used for py-tango unit-testing <p data-bbox="810 450 922 474">Changes:</p> <ul data-bbox="919 495 1385 1144" style="list-style-type: none"> <li data-bbox="919 495 1385 555">• Issue #51: Refactor platform specific code in setup file <li data-bbox="919 573 1385 633">• Issue #67: Comply with PEP 440 for pre-releases <li data-bbox="919 651 1385 712">• Pull Request #70: Add unit-testing for the server API <li data-bbox="919 730 1385 790">• Pull Request #70: Configure Travis CI for continuous integration <li data-bbox="919 808 1385 869">• Pull Request #76: Add unit-testing for the client API <li data-bbox="919 887 1385 947">• Pull Request #78: Update the python version classifiers <li data-bbox="919 965 1385 1025">• Pull Request #80: Move tango object server to its own module <li data-bbox="919 1043 1385 1144">• Pull Request #90: The metaclass definition for tango devices is no longer mandatory <p data-bbox="810 1162 927 1187">Bug fixes:</p> <ul data-bbox="919 1207 1385 2018" style="list-style-type: none"> <li data-bbox="919 1207 1385 1267">• Issue #24: Fix dev_status dangling pointer bug <li data-bbox="919 1285 1385 1346">• Issue #57: Fix dev_state/status to be gevent safe <li data-bbox="919 1364 1385 1424">• Issue #58: Server gevent mode internal call hangs <li data-bbox="919 1442 1385 1503">• Pull Request #62: Several fixes in tango.databases <li data-bbox="919 1520 1385 1581">• Pull Request #63: Follow up on issue #21 (Fix Group.get_device method) <li data-bbox="919 1599 1385 1693">• Issue #64: Fix AttributeProxy.__dev_proxy to be initialized with python internals <li data-bbox="919 1711 1385 1771">• Issue #74: Fix hanging with an asynchronous tango server fails to start <li data-bbox="919 1789 1385 1850">• Pull Request #81: Fix DeviceImpl documentation <li data-bbox="919 1868 1385 1928">• Issue #82: Fix attribute completion for device proxies with IPython >= 4 <li data-bbox="919 1946 1385 2007">• Issue #84: Fix gevent threadpool exceptions

continues on next page

Table 2 – continued from previous page

Version	Changes
9.2.0	<p>9.2.0 release.</p> <p>Features:</p> <ul style="list-style-type: none"> • Issue #37: Add <code>display_level</code> and <code>polling_period</code> as optional arguments to command decorator <p>Bug fixes:</p> <ul style="list-style-type: none"> • Fix cache problem when using <i>DeviceProxy</i> through an <i>AttributeProxy</i> • Fix compilation on several platforms • Issue #19: Defining new members in <i>DeviceProxy</i> has side effects • Fixed bug in <i>beacon.add_device</i> • Fix for <i>get_device_list</i> if <code>server_name</code> is '*' • Fix <i>get_device_attribute_property2</i> if <code>prop_attr</code> is not <code>None</code> • Accept <code>StdStringVector</code> in <i>put_device_property</i> • Map 'int' to <code>DevLong64</code> and 'uint' to <code>DevULong64</code> • Issue #22: Fix <i>push_data_ready_event()</i> deadlock • Issue #28: Fix compilation error for <code>constants.cpp</code> • Issue #21: Fix <i>Group.get_device</i> method • Issue #33: Fix internal server documentation <p>Changes:</p> <ul style="list-style-type: none"> • Move ITango to another project • Use <i>setuptools</i> instead of <i>distutils</i> • Add <i>six</i> as a requirement • Refactor directory structure • Rename <i>PyTango</i> module to <i>tango</i> (<code>import PyTango</code> still works for backward compatibility) • Add a ReST readme for GitHub and PyPI <p>ITango changes (moved to another project):</p> <ul style="list-style-type: none"> • Fix itango event logger for python 3 • Avoid deprecation warning with IPython 4.x • Use entry points instead of scripts

continues on next page

Table 2 – continued from previous page

Version	Changes
9.2.0a	9.2 alpha release. Missing: <ul style="list-style-type: none"> • writable pipes (client and server) • dynamic commands (server) • device interface change event (client and server) • pipe event (client and server) Bug fixes: <ul style="list-style-type: none"> • 776: [pytango][8.1.8] SyntaxError: invalid syntax
8.1.9	Features: <ul style="list-style-type: none"> • PR #2: asyncio support for both client and server API • PR #6: Expose AutoTangoMonitor and AutoTangoAllowThreads Bug fixes: <ul style="list-style-type: none"> • PR #31: Get -l flags from pkg-config • PR #15: Rename itango script to itango3 for python3 • PR #14: Avoid deprecation warning with IPython 4.x

continues on next page

Table 2 – continued from previous page

Version	Changes
8.1.8	<p>Features:</p> <ul style="list-style-type: none"> • PR #3: Add a run_server class method to Device • PR #4: Add device inheritance • 110: device property with auto update in database <p>Bug fixes:</p> <ul style="list-style-type: none"> • 690: Description attribute property • 700: [pytango] useless files in the source distribution • 701: Memory leak in command with list argument • 704: Assertion failure when calling command with string array input type • 705: Support boost_python lib name on Gentoo • 714: Memory leak in PyTango for direct server command calls • 718: OverflowErrors with float types in 8.1.6 • 724: PyTango Device-Proxy.command_inout(<str>) memory leaks • 736: pytango FTBFS with python 3.4 • 747: PyTango event callback in gevent mode gets called in non main thread
8.1.6	<p>Bug fixes:</p> <ul style="list-style-type: none"> • 698: PyTango.Util discrepancy • 697: PyTango.server.run does not accept old Device style classes
8.1.5	<p>Bug fixes:</p> <ul style="list-style-type: none"> • 687: [pytango] 8.1.4 unexpected files in the source package • 688: PyTango 8.1.4 new style server commands don't work

continues on next page

Table 2 – continued from previous page

Version	Changes
8.1.4	Features: <ul style="list-style-type: none"> • 107: Nice to check Tango/PyTango version at runtime Bug fixes: <ul style="list-style-type: none"> • 659: segmentation fault when unsubscribing from events • 664: problem while installing PyTango 8.1.1 with pip (using pip 1.4.1) • 678: [pytango] 8.1.2 unexpected files in the source package • 679: PyTango.server tries to import missing <code>__builtin__</code> module on Python 3 • 680: Cannot import PyTango.server.run • 686: Device property substitution for a multi-device server
8.1.3	<i>SKIPPED</i>
8.1.2	Features: <ul style="list-style-type: none"> • 98: PyTango.server.server_run needs additional <code>post_init_callback</code> parameter • 102: DevEncoded attribute should support a python buffer object • 103: Make creation of *EventData objects possible in PyTango Bug fixes: <ul style="list-style-type: none"> • 641: python3 error handling issue • 648: PyTango unicode method parameters fail • 649: <code>write_attribute</code> of <code>spectrum/image</code> fails in PyTango without numpy • 650: [pytango] 8.1.1 not compatible with ipyton 1.2.0-rc1 • 651: PyTango segmentation fault when run a DS that use <code>attr_data.py</code> • 660: <code>command_inout_async</code> (polling mode) fails • 666: PyTango shutdown sometimes blocks.

continues on next page

Table 2 – continued from previous page

Version	Changes
8.1.1	<p>Features:</p> <ul style="list-style-type: none"> • Implemented tango C++ 8.1 API <p>Bug fixes:</p> <ul style="list-style-type: none"> • 527: set_value() for ULong64 • 573: [pytango] python3 error with unregistered device • 611: URGENT fail to write attribute with PyTango 8.0.3 • 612: [pytango][8.0.3] failed to build from source on s390 • 615: Threading problem when setting a DevULong64 attribute • 622: PyTango broken when running on Ubuntu 13 • 626: attribute_history extraction can raised an exception • 628: Problem in installing PyTango 8.0.3 on Scientific Linux 6 • 635: Reading of ULong64 attributes does not work • 636: PyTango log messages are not filtered by level • 637: [pytango] segfault doing write_attribute on Group
8.1.0	<i>SKIPPED</i>
8.0.3	<p>Features:</p> <ul style="list-style-type: none"> • 88: Implement Util::server_set_event_loop method in python <p>Bug fixes:</p> <ul style="list-style-type: none"> • 3576353: [pytango] segfault on 'Restart-Server' • 3579062: [pytango] Attribute missing methods • 3586337: [pytango] Some DeviceClass methods are not python safe • 3598514: DeviceProxy.__setattr__ break python's descriptors • 3607779: [pytango] IPython 0.10 error • 598: Import DLL by PyTango failed on windows • 605: [pytango] use distutils.version module

continues on next page

Table 2 – continued from previous page

Version	Changes
8.0.2	Bug fixes: <ul style="list-style-type: none"> • 3570970: [pytango] problem during the python3 building • 3570971: [pytango] itango does not work without qtconsole • 3570972: [pytango] warning/error when building 8.0.0 • 3570975: [pytango] problem during use of python3 version • 3574099: [pytango] compile error with gcc < 4.5
8.0.1	<i>SKIPPED</i>
8.0.0	Features: <ul style="list-style-type: none"> • Implemented tango C++ 8.0 API • Python 3k compatible Bug fixes: <ul style="list-style-type: none"> • 3023857: DevEncoded write attribute not supported • 3521545: [pytango] problem with tango profile • 3530535: PyTango group writting fails • 3564959: EncodedAttribute.encode_xxx() methods don't accept bytearray
7.2.4	Bug fixes: <ul style="list-style-type: none"> • 551: [pytango] Some DeviceClass methods are not python safe
7.2.3	Features: <ul style="list-style-type: none"> • 3495607: DeviceClass.device_name_factory is missing Bug fixes: <ul style="list-style-type: none"> • 3103588: documentation of PyTango.Attribute.Group • 3458336: Problem with pytango 7.2.2 • 3463377: PyTango memory leak in read encoded attribute • 3487930: [pytango] wrong python dependency • 3511509: Attribute.set_value_date_quality for encoded does not work • 3514457: [pytango] TANGO_HOST multi-host support • 3520739: command_history(...) in PyTango

continues on next page

Table 2 – continued from previous page

Version	Changes
7.2.2	<p>Features:</p> <ul style="list-style-type: none"> • 3305251: DS dynamic attributes discards some Attr properties • 3365792: DeviceProxy.<cmd_name> could be documented • 3386079: add support for ipython 0.11 • 3437654: throw python exception as tango exception • 3447477: spock profile installation <p>Bug fixes:</p> <ul style="list-style-type: none"> • 3372371: write attribute of DevEncoded doesn't work • 3374026: [pytango] pyflakes warning • 3404771: PyTango.MultiAttribute.get_attribute_list missing • 3405580: PyTango.MultiClassAttribute missing
7.2.1	<i>SKIPPED</i>
7.2.0	<p>Features:</p> <ul style="list-style-type: none"> • 3286678: Add missing EncodedAttribute JPEG methods
7.1.6	<p>Bug fixes:</p> <ul style="list-style-type: none"> • 7.1.5 distribution is missing some files
7.1.5	<p>Bug fixes:</p> <ul style="list-style-type: none"> • 3284174: 7.1.4 does not build with gcc 4.5 and tango 7.2.6 • 3284265: [pytango][7.1.4] a few files without licence and copyright • 3284318: copyleft vs copyright • 3284434: [pytango][doc] few ERROR during the doc generation • 3284435: [pytango][doc] few warning during the doc generation • 3284440: [pytango][spock] the profile can't be installed • 3285185: PyTango Device Server does not load Class Properties values • 3286055: PyTango 7.1.x DS using Tango C++ 7.2.x seg faults on exit

continues on next page

Table 2 – continued from previous page

Version	Changes
7.1.4	<p>Features:</p> <ul style="list-style-type: none"> • 3274309: Generic Callback for events <p>Bug fixes:</p> <ul style="list-style-type: none"> • 3011775: Seg Faults due to removed dynamic attributes • 3105169: PyTango 7.1.3 does not compile with Tango 7.2.X • 3107243: spock profile does not work with python 2.5 • 3124427: PyTango.WAttribute.set_max_value() changes min value • 3170399: Missing documentation about is_<attr>_allowed method • 3189082: Missing get_properties() for Attribute class • 3196068: delete_device() not called after server_admin.Kill() • 3257286: Binding crashes when reading a WRITE string attribute • 3267628: DP.read_attribute(, extract=List/tuple) write value is wrong • 3274262: Database.is_multi_tango_host missing • 3274319: EncodedAttribute is missing in PyTango (<= 7.1.3) • 3277269: read_attribute(DevEncoded) is not numpy as expected • 3278946: DeviceAttribute copy constructor is not working <p>Documentation:</p> <ul style="list-style-type: none"> • Added <i>The Utilities API</i> chapter • Added <i>Encoded API</i> chapter • Improved <i>Write a server (original API)</i> chapter

continues on next page

Table 2 – continued from previous page

Version	Changes
7.1.3	<p>Features:</p> <ul style="list-style-type: none"> • tango logging with print statement • tango logging with decorators • from sourceforge: • 3060380: ApiUtil should be exported to Py-Tango <p>Bug fixes:</p> <ul style="list-style-type: none"> • added licence header to all source code files • spock didn't work without TANGO_HOST env. variable (it didn't recognize tangorc) • spock should give a proper message if it tries to be initialized outside ipython • 3048798: licence issue GPL != LGPL • 3073378: DeviceImpl.signal_handler raising exception crashes DS • 3088031: Python DS unable to read Dev-VarBooleanArray property • 3102776: PyTango 7.1.2 does not work with python 2.4 & boost 1.33.0 • 3102778: Fix compilation warnings in linux

continues on next page

Table 2 – continued from previous page

Version	Changes
7.1.2	<p>Features:</p> <ul style="list-style-type: none"> • 2995964: Dynamic device creation • 3010399: The DeviceClass.get_device_list that exists in C++ is missing • 3023686: Missing DeviceProxy.<attribute name> • 3025396: DeviceImpl is missing some CORBA methods • 3032005: IPython extension for PyTango • 3033476: Make client objects pickable • 3039902: PyTango.Util.add_class would be useful <p>Bug fixes:</p> <ul style="list-style-type: none"> • 2975940: DS command with DevVarCharArray return type fails • 3000467: DeviceProxy.unlock is LOCKING instead of unlocking! • 3010395: Util.get_device_* methods don't work • 3010425: Database.dev_name does not work • 3016949: command_inout_asynch callback does not work • 3020300: PyTango does not compile with gcc 4.1.x • 3030399: Database.put(delete)_attribute_alias generates segfault
7.1.1	<p>Features:</p> <ul style="list-style-type: none"> • Improved setup script • Interfaced with PyPI • Cleaned build script warnings due to unclean python C++ macro definitions • 2985993: PyTango numpy command support • 2971217: PyTango.GroupAttrReplyList slicing <p>Bug fixes:</p> <ul style="list-style-type: none"> • 2983299: Database.put_property() deletes the property • 2953689: can not write_attribute scalar/spectrum/image • 2953030: PyTango doc installation

continues on next page

Table 2 – continued from previous page

Version	Changes
7.1.0	<p>Features:</p> <ul style="list-style-type: none"> • 2908176: <code>read_*</code>, <code>write_*</code> and <code>is_*_allowed()</code> methods can now be defined • 2941036: TimeVal conversion to time and datetime • added str representation on Attr, Attribute, DeviceImpl and DeviceClass <p>Bug fixes:</p> <ul style="list-style-type: none"> • 2903755: <code>get_device_properties()</code> bug reading DevString properties • 2909927: <code>PyTango.Group.read_attribute()</code> return values • 2914194: DevEncoded does not work • 2916397: <code>PyTango.DeviceAttribute</code> copy constructor does not work • 2936173: <code>PyTango.Group.read_attributes()</code> fails • 2949099: Missing <code>PyTango.Except.print_error_stack</code>

continues on next page

Table 2 – continued from previous page

Version	Changes
7.1.0rc1	<p>Features:</p> <ul style="list-style-type: none"> • <code>v = image_attribute.get_write_value()</code> returns square sequences (arrays of arrays, or numpy objects) now instead of flat lists. Also for spectrum attributes a numpy is returned by default now instead. • <code>image_attribute.set_value(v)</code> accepts numpy arrays now or square sequences instead of just flat lists. So, <code>dim_x</code> and <code>dim_y</code> are useless now. Also the numpy path is faster. • new enum <code>AttrSerialModel</code> • <code>Attribute</code> new methods: <code>set(get)_attr_serial_model</code>, <code>set_change_event</code>, <code>set_archive_event</code>, <code>is_change_event</code>, <code>is_check_change_event</code>, <code>is_archive_criteria</code>, <code>is_check_archive_criteria</code>, <code>remove_configuration</code> • added support for numpy scalars in tango operations like <code>write_attribute</code> (ex: now a <code>DEV_LONG</code> attribute can receive a <code>numpy.int32</code> argument in a <code>write_attribute</code> method call) <p>Bug fixes:</p> <ul style="list-style-type: none"> • <code>DeviceImpl.set_value</code> for scalar attributes • <code>DeviceImpl.push_***_event</code> • server commands with <code>DevVar***StringArray</code> as parameter or as return type • in windows, a bug in <code>PyTango.Util</code> prevented servers from starting up • <code>DeviceImpl.get_device_properties</code> for string properties assigns only first character of string to object member instead of entire string • added missing methods to <code>Util</code> • exported <code>SubDevDiag</code> class • error in read/events of attributes of type <code>DevBoolean READ_WRITE</code> • error in automatic unsubscribe events of <code>DeviceProxy</code> when the object disappears (happens only on some compilers with some optimization flags) • fix possible bug when comparing attribute names in <code>DeviceProxy</code> • pretty print of <code>DevFailed</code> -> fix deprecation warning in python 2.6 • device class properties where not properly fetched when there is no property value defined
10.2. Version history	<p style="text-align: right;">271</p> <ul style="list-style-type: none"> • memory leak when converting <code>DevFailed</code> exceptions from C++ to python • python device server file without extension

Table 2 – continued from previous page

Version	Changes
---------	---------

INDEXES

- [modindex](#)
- [genindex](#)

Last update: Apr 30, 2020

PYTHON MODULE INDEX

t

tango, 21

tango.server, 96

A

AccessControlType (class in tango), 93
 add() (tango.Group method), 74
 add_attribute() (tango.LatestDeviceImpl method), 118
 add_attribute() (tango.server.Device method), 100
 add_class() (tango.Util method), 155
 add_command() (tango.LatestDeviceImpl method), 118
 add_command() (tango.server.Device method), 100
 add_Cpp_TgClass() (tango.Util method), 155
 add_device() (tango.Database method), 162
 add_logging_target() (tango.DeviceProxy method), 30
 add_server() (tango.Database method), 162
 add_TgClass() (tango.Util method), 155
 adm_name() (tango.DeviceProxy method), 30
 alias() (tango.DeviceProxy method), 30
 always_executed_hook() (tango.LatestDeviceImpl method), 118
 always_executed_hook() (tango.server.Device method), 101
 ApiUtil (class in tango), 82
 append_status() (tango.LatestDeviceImpl method), 119
 append_status() (tango.server.Device method), 101
 ArchiveEventInfo (class in tango), 89
 asyn_req_type (class in tango), 93
 AsyncCall, 202
 AsyncReplyNotArrived, 203
 Attr (class in tango), 136
 AttrConfEventData (class in tango), 90
 AttrDataFormat (class in tango), 93
 AttrReqType (class in tango), 92
 Attribute (class in tango), 140
 attribute (class in tango.server), 111
 attribute_history() (tango.DeviceProxy method), 30
 attribute_list_query() (tango.DeviceProxy method), 31
 attribute_list_query_ex() (tango.DeviceProxy method), 31
 attribute_query() (tango.DeviceProxy method), 31

AttributeAlarmInfo (class in tango), 84
 AttributeDimension (class in tango), 84
 AttributeEventInfo (class in tango), 89
 AttributeInfo (class in tango), 84
 AttributeInfoEx (class in tango), 84
 AttributeProxy (class in tango), 61
 AttrQuality (class in tango), 93
 AttrReadEvent (class in tango), 89
 AttrWriteType (class in tango), 93
 AttrWrittenEvent (class in tango), 89

B

black_box() (tango.DeviceProxy method), 31
 build_connection() (tango.Database method), 163

C

cancel_all_polling_asynch_request() (tango.DeviceProxy method), 31
 cancel_asynch_request() (tango.DeviceProxy method), 31
 cb_sub_model (class in tango), 93
 ChangeEventInfo (class in tango), 90
 check_access_control() (tango.Database method), 163
 check_alarm() (tango.Attribute method), 140
 check_alarm() (tango.MultiAttribute method), 148
 check_command_exists() (tango.LatestDeviceImpl method), 119
 check_command_exists() (tango.server.Device method), 101
 check_tango_host() (tango.Database method), 163
 class_property (class in tango.server), 115
 CmdArgType (class in tango), 91
 CmdDoneEvent (class in tango), 89
 command() (in module tango.server), 113
 command_history() (tango.DeviceProxy method), 32
 command_inout() (tango.DeviceProxy method), 32
 command_inout() (tango.Group method), 74
 command_inout_asynch() (tango.DeviceProxy method), 32
 command_inout_asynch() (tango.Group method), 74

- `command_inout_raw()` (*tango.DeviceProxy method*), 33
`command_inout_reply()` (*tango.DeviceProxy method*), 34
`command_inout_reply()` (*tango.Group method*), 75
`command_inout_reply_raw()` (*tango.DeviceProxy method*), 34
`command_list_query()` (*tango.DeviceProxy method*), 35
`command_query()` (*tango.DeviceProxy method*), 35
`CommandInfo` (*class in tango*), 86
`CommunicationFailed`, 201
`connect()` (*tango.DeviceProxy method*), 35
`connect_db()` (*tango.Util method*), 155
`ConnectionFailed`, 201
`contains()` (*tango.Group method*), 75
`create_device()` (*tango.DeviceClass method*), 130
`create_device()` (*tango.Util method*), 156
- ## D
- `Database` (*class in tango*), 162
`DataReadyEventData` (*class in tango*), 90
`DbDatum` (*class in tango*), 188
`DbDevExportInfo` (*class in tango*), 188
`DbDevImportInfo` (*class in tango*), 188
`DbDevInfo` (*class in tango*), 188
`DbHistory` (*class in tango*), 189
`DbServerInfo` (*class in tango*), 189
`debug_stream()` (*tango.LatestDeviceImpl method*), 119
`debug_stream()` (*tango.server.Device method*), 101
`DebugIt` (*class in tango*), 134
`decode_gray16()` (*tango.EncodedAttribute method*), 189
`decode_gray8()` (*tango.EncodedAttribute method*), 190
`decode_rgb32()` (*tango.EncodedAttribute method*), 190
`delete_attribute_alias()` (*tango.Database method*), 164
`delete_class_attribute_property()` (*tango.Database method*), 164
`delete_class_pipe_property()` (*tango.Database method*), 164
`delete_class_property()` (*tango.Database method*), 164
`delete_device()` (*tango.Database method*), 165
`delete_device()` (*tango.DeviceClass method*), 130
`delete_device()` (*tango.LatestDeviceImpl method*), 119
`delete_device()` (*tango.server.Device method*), 101
`delete_device()` (*tango.Util method*), 156
`delete_device_alias()` (*tango.Database method*), 165
`delete_device_attribute_property()` (*tango.Database method*), 165
`delete_device_pipe_property()` (*tango.Database method*), 165
`delete_device_property()` (*tango.Database method*), 166
`delete_property()` (*tango.AttributeProxy method*), 61
`delete_property()` (*tango.Database method*), 166
`delete_property()` (*tango.DeviceProxy method*), 35
`delete_server()` (*tango.Database method*), 167
`delete_server_info()` (*tango.Database method*), 167
`description()` (*tango.DeviceProxy method*), 36
`dev_name()` (*tango.DeviceProxy method*), 36
`dev_state()` (*tango.LatestDeviceImpl method*), 119
`dev_status()` (*tango.LatestDeviceImpl method*), 120
`DevCommandInfo` (*class in tango*), 86
`DevError` (*class in tango*), 201
`DevFailed`, 201
`Device` (*class in tango.server*), 100
`device_destroyer()` (*tango.DeviceClass method*), 131
`device_factory()` (*tango.DeviceClass method*), 131
`device_name_factory()` (*tango.DeviceClass method*), 131
`device_property` (*class in tango.server*), 115
`DeviceAttribute` (*class in tango*), 87
`DeviceAttributeConfig` (*class in tango*), 85
`DeviceAttributeHistory` (*class in tango*), 91
`DeviceClass` (*class in tango*), 130
`DeviceData` (*class in tango*), 88
`DeviceDataHistory` (*class in tango*), 91
`DeviceInfo` (*class in tango*), 86
`DeviceProxy` (*class in tango*), 29
`DeviceProxy()` (*in module tango.futures*), 81
`DeviceProxy()` (*in module tango.gevent*), 81
`DeviceUnlocked`, 203
`DevSource` (*class in tango*), 94
`DevState` (*class in tango*), 94
`disable()` (*tango.Group method*), 76
`DispLevel` (*class in tango*), 94
`dyn_attr()` (*tango.DeviceClass method*), 131
- ## E
- `enable()` (*tango.Group method*), 76
`encode_gray16()` (*tango.EncodedAttribute method*), 191
`encode_gray8()` (*tango.EncodedAttribute method*), 192
`encode_jpeg_gray8()` (*tango.EncodedAttribute method*), 192

- encode_jpeg_rgb24() (*tango.EncodedAttribute method*), 193
 encode_jpeg_rgb32() (*tango.EncodedAttribute method*), 194
 encode_rgb24() (*tango.EncodedAttribute method*), 194
 EncodedAttribute (*class in tango*), 189
 environment variable
 PYTANGO_GREEN_MODE, 13
 TANGO_HOST, 3, 4, 205
 error_stream() (*tango.LatestDeviceImpl method*), 120
 error_stream() (*tango.server.Device method*), 101
 ErrorIt (*class in tango*), 135
 ErrSeverity (*class in tango*), 94
 event_queue_size() (*tango.AttributeProxy method*), 62
 event_queue_size() (*tango.DeviceProxy method*), 36
 EventCallback (*class in tango.utils*), 195
 EventData (*class in tango*), 90
 EventSystemFailed, 203
 EventType (*class in tango*), 93
 Except (*class in tango*), 201
 export_device() (*tango.Database method*), 167
 export_device() (*tango.DeviceClass method*), 131
 export_event() (*tango.Database method*), 167
 export_server() (*tango.Database method*), 167
 extract() (*tango.DeviceData method*), 88
 ExtractAs (*tango.DeviceAttribute attribute*), 87
- ## F
- fatal_stream() (*tango.LatestDeviceImpl method*), 120
 fatal_stream() (*tango.server.Device method*), 101
 FatalIt (*class in tango*), 135
- ## G
- get_access_control() (*tango.DeviceProxy method*), 36
 get_access_except_errors() (*tango.Database method*), 168
 get_access_right() (*tango.DeviceProxy method*), 37
 get_alias() (*tango.Database method*), 168
 get_alias_from_attribute() (*tango.Database method*), 168
 get_alias_from_device() (*tango.Database method*), 168
 get_assoc() (*tango.Attr method*), 136
 get_assoc_ind() (*tango.Attribute method*), 140
 get_assoc_name() (*tango.Attribute method*), 140
 get_asynch_cb_sub_model() (*tango.ApiUtil method*), 82
 get_asynch_replies() (*tango.ApiUtil method*), 82
 get_asynch_replies() (*tango.DeviceProxy method*), 37
 get_attr_by_ind() (*tango.MultiAttribute method*), 149
 get_attr_by_name() (*tango.MultiAttribute method*), 149
 get_attr_ind_by_name() (*tango.MultiAttribute method*), 149
 get_attr_min_poll_period() (*tango.LatestDeviceImpl method*), 120
 get_attr_min_poll_period() (*tango.server.Device method*), 102
 get_attr_nb() (*tango.MultiAttribute method*), 149
 get_attr_poll_ring_depth() (*tango.LatestDeviceImpl method*), 120
 get_attr_poll_ring_depth() (*tango.server.Device method*), 102
 get_attr_serial_model() (*tango.Attribute method*), 140
 get_attribute_alias() (*tango.Database method*), 168
 get_attribute_alias_list() (*tango.Database method*), 169
 get_attribute_config() (*tango.DeviceProxy method*), 37
 get_attribute_config_ex() (*tango.DeviceProxy method*), 37
 get_attribute_from_alias() (*tango.Database method*), 169
 get_attribute_list() (*tango.DeviceProxy method*), 38
 get_attribute_list() (*tango.MultiAttribute method*), 150
 get_attribute_name() (*tango.DbHistory method*), 189
 get_attribute_poll_period() (*tango.DeviceProxy method*), 38
 get_attribute_poll_period() (*tango.LatestDeviceImpl method*), 121
 get_attribute_poll_period() (*tango.server.Device method*), 102
 get_cl_name() (*tango.Attr method*), 136
 get_class_attribute_list() (*tango.Database method*), 169
 get_class_attribute_property() (*tango.Database method*), 169
 get_class_attribute_property_history() (*tango.Database method*), 170
 get_class_for_device() (*tango.Database method*), 170
 get_class_inheritance_for_device() (*tango.Database method*), 170
 get_class_list() (*tango.Database method*), 171
 get_class_list() (*tango.Util method*), 156
 get_class_pipe_list() (*tango.Database*

- method*), 171
- `get_class_pipe_property()` (*tango.Database method*), 171
- `get_class_pipe_property_history()` (*tango.Database method*), 171
- `get_class_properties()` (*tango.Attr method*), 136
- `get_class_property()` (*tango.Database method*), 172
- `get_class_property_history()` (*tango.Database method*), 172
- `get_class_property_list()` (*tango.Database method*), 172
- `get_cmd_by_name()` (*tango.DeviceClass method*), 131
- `get_cmd_min_poll_period()` (*tango.LatestDeviceImpl method*), 121
- `get_cmd_min_poll_period()` (*tango.server.Device method*), 102
- `get_cmd_poll_ring_depth()` (*tango.LatestDeviceImpl method*), 121
- `get_cmd_poll_ring_depth()` (*tango.server.Device method*), 102
- `get_command_config()` (*tango.DeviceProxy method*), 38
- `get_command_list()` (*tango.DeviceClass method*), 131
- `get_command_list()` (*tango.DeviceProxy method*), 39
- `get_command_poll_period()` (*tango.DeviceProxy method*), 39
- `get_command_poll_period()` (*tango.LatestDeviceImpl method*), 121
- `get_command_poll_period()` (*tango.server.Device method*), 103
- `get_config()` (*tango.AttributeProxy method*), 62
- `get_cvs_location()` (*tango.DeviceClass method*), 132
- `get_cvs_tag()` (*tango.DeviceClass method*), 132
- `get_data()` (*tango.GroupAttrReply method*), 80
- `get_data()` (*tango.GroupCmdReply method*), 80
- `get_data_format()` (*tango.Attribute method*), 140
- `get_data_raw()` (*tango.GroupCmdReply method*), 80
- `get_data_size()` (*tango.Attribute method*), 141
- `get_data_type()` (*tango.Attribute method*), 141
- `get_database()` (*tango.Util method*), 157
- `get_date()` (*tango.Attribute method*), 141
- `get_date()` (*tango.DbHistory method*), 189
- `get_date()` (*tango.DeviceAttribute method*), 87
- `get_db_host()` (*tango.DeviceProxy method*), 39
- `get_db_port()` (*tango.DeviceProxy method*), 39
- `get_db_port_num()` (*tango.DeviceProxy method*), 39
- `get_dev_host()` (*tango.DeviceProxy method*), 39
- `get_dev_idl_version()` (*tango.LatestDeviceImpl method*), 121
- `get_dev_idl_version()` (*tango.server.Device method*), 103
- `get_dev_port()` (*tango.DeviceProxy method*), 40
- `get_device_alias()` (*tango.Database method*), 173
- `get_device_alias_list()` (*tango.Database method*), 173
- `get_device_attr()` (*tango.LatestDeviceImpl method*), 121
- `get_device_attr()` (*tango.server.Device method*), 103
- `get_device_attribute_list()` (*tango.Database method*), 173
- `get_device_attribute_property()` (*tango.Database method*), 173
- `get_device_attribute_property_history()` (*tango.Database method*), 174
- `get_device_by_name()` (*tango.Util method*), 157
- `get_device_class_list()` (*tango.Database method*), 174
- `get_device_db()` (*tango.DeviceProxy method*), 40
- `get_device_domain()` (*tango.Database method*), 174
- `get_device_exported()` (*tango.Database method*), 175
- `get_device_exported_for_class()` (*tango.Database method*), 175
- `get_device_family()` (*tango.Database method*), 175
- `get_device_from_alias()` (*tango.Database method*), 175
- `get_device_info()` (*tango.Database method*), 175
- `get_device_list()` (*tango.DeviceClass method*), 132
- `get_device_list()` (*tango.Group method*), 76
- `get_device_list()` (*tango.Util method*), 157
- `get_device_list_by_class()` (*tango.Util method*), 157
- `get_device_member()` (*tango.Database method*), 176
- `get_device_name()` (*tango.Database method*), 176
- `get_device_pipe_list()` (*tango.Database method*), 176
- `get_device_pipe_property()` (*tango.Database method*), 176
- `get_device_pipe_property_history()` (*tango.Database method*), 177
- `get_device_properties()` (*tango.LatestDeviceImpl method*), 121
- `get_device_properties()` (*tango.server.Device method*), 103
- `get_device_property()` (*tango.Database method*), 177
- `get_device_property_history()` (*tango.Database method*), 177
- `get_device_property_list()`

- (*tango.Database method*), 178
- `get_device_proxy()` (*tango.AttributeProxy method*), 63
- `get_device_service_list()` (*tango.Database method*), 178
- `get_disp_level()` (*tango.Attr method*), 136
- `get_doc_url()` (*tango.DeviceClass method*), 132
- `get_ds_exec_name()` (*tango.Util method*), 157
- `get_ds_inst_name()` (*tango.Util method*), 157
- `get_ds_name()` (*tango.Util method*), 158
- `get_dserver_device()` (*tango.Util method*), 158
- `get_enum_labels()` (*in module tango.utils*), 195
- `get_err_stack()` (*tango.DeviceAttribute method*), 87
- `get_events()` (*tango.AttributeProxy method*), 63
- `get_events()` (*tango.DeviceProxy method*), 40
- `get_events()` (*tango.utils.EventCallback method*), 195
- `get_exported_flag()` (*tango.LatestDeviceImpl method*), 122
- `get_exported_flag()` (*tango.server.Device method*), 103
- `get_file_name()` (*tango.Database method*), 178
- `get_format()` (*tango.Attr method*), 136
- `get_fqdn()` (*tango.DeviceProxy method*), 40
- `get_from_env_var()` (*tango.DeviceProxy method*), 40
- `get_fully_qualified_name()` (*tango.Group method*), 77
- `get_green_mode()` (*in module tango*), 81
- `get_green_mode()` (*tango.DeviceProxy method*), 41
- `get_home()` (*in module tango.utils*), 198
- `get_host_list()` (*tango.Database method*), 178
- `get_host_name()` (*tango.Util method*), 158
- `get_host_server_list()` (*tango.Database method*), 179
- `get_idl_version()` (*tango.DeviceProxy method*), 41
- `get_info()` (*tango.Database method*), 179
- `get_instance_name_list()` (*tango.Database method*), 179
- `get_label()` (*tango.Attribute method*), 141
- `get_last_event_date()` (*tango.AttributeProxy method*), 63
- `get_last_event_date()` (*tango.DeviceProxy method*), 41
- `get_locker()` (*tango.DeviceProxy method*), 41
- `get_logger()` (*tango.LatestDeviceImpl method*), 122
- `get_logger()` (*tango.server.Device method*), 103
- `get_logging_level()` (*tango.DeviceProxy method*), 41
- `get_logging_target()` (*tango.DeviceProxy method*), 42
- `get_max_dim_x()` (*tango.Attribute method*), 141
- `get_max_dim_y()` (*tango.Attribute method*), 141
- `get_max_value()` (*tango.WAttribute method*), 147
- `get_memorized()` (*tango.Attr method*), 136
- `get_memorized_init()` (*tango.Attr method*), 136
- `get_min_poll_period()` (*tango.LatestDeviceImpl method*), 122
- `get_min_poll_period()` (*tango.server.Device method*), 103
- `get_min_value()` (*tango.WAttribute method*), 147
- `get_name()` (*tango.Attr method*), 137
- `get_name()` (*tango.Attribute method*), 141
- `get_name()` (*tango.DbHistory method*), 189
- `get_name()` (*tango.DeviceClass method*), 132
- `get_name()` (*tango.Group method*), 77
- `get_name()` (*tango.LatestDeviceImpl method*), 122
- `get_name()` (*tango.server.Device method*), 104
- `get_non_auto_polled_attr()` (*tango.LatestDeviceImpl method*), 122
- `get_non_auto_polled_attr()` (*tango.server.Device method*), 104
- `get_non_auto_polled_cmd()` (*tango.LatestDeviceImpl method*), 122
- `get_non_auto_polled_cmd()` (*tango.server.Device method*), 104
- `get_object_list()` (*tango.Database method*), 179
- `get_object_property_list()` (*tango.Database method*), 179
- `get_pid()` (*tango.Util method*), 158
- `get_pid_str()` (*tango.Util method*), 158
- `get_pipe_config()` (*tango.DeviceProxy method*), 42
- `get_poll_old_factor()` (*tango.LatestDeviceImpl method*), 123
- `get_poll_old_factor()` (*tango.server.Device method*), 104
- `get_poll_period()` (*tango.AttributeProxy method*), 64
- `get_poll_ring_depth()` (*tango.LatestDeviceImpl method*), 123
- `get_poll_ring_depth()` (*tango.server.Device method*), 104
- `get_polled_attr()` (*tango.LatestDeviceImpl method*), 123
- `get_polled_attr()` (*tango.server.Device method*), 104
- `get_polled_cmd()` (*tango.LatestDeviceImpl method*), 123
- `get_polled_cmd()` (*tango.server.Device method*), 104
- `get_polling_period()` (*tango.Attr method*), 137
- `get_polling_period()` (*tango.Attribute method*), 141
- `get_polling_threads_pool_size()` (*tango.Util method*), 158
- `get_prev_state()` (*tango.LatestDeviceImpl method*), 123
- `get_prev_state()` (*tango.server.Device method*), 104

- 105
- `get_properties()` (*tango.Attribute* method), 142
- `get_property()` (*tango.AttributeProxy* method), 64
- `get_property()` (*tango.Database* method), 180
- `get_property()` (*tango.DeviceProxy* method), 42
- `get_property_forced()` (*tango.Database* method), 180
- `get_property_history()` (*tango.Database* method), 181
- `get_property_list()` (*tango.DeviceProxy* method), 43
- `get_quality()` (*tango.Attribute* method), 142
- `get_serial_model()` (*tango.Util* method), 158
- `get_server_class_list()` (*tango.Database* method), 181
- `get_server_info()` (*tango.Database* method), 181
- `get_server_list()` (*tango.Database* method), 181
- `get_server_name_list()` (*tango.Database* method), 182
- `get_server_version()` (*tango.Util* method), 158
- `get_services()` (*tango.Database* method), 182
- `get_size()` (*tango.Group* method), 77
- `get_source()` (*tango.DeviceProxy* method), 43
- `get_state()` (*tango.LatestDeviceImpl* method), 123
- `get_state()` (*tango.server.Device* method), 105
- `get_status()` (*tango.LatestDeviceImpl* method), 123
- `get_status()` (*tango.server.Device* method), 105
- `get_sub_dev_diag()` (*tango.Util* method), 159
- `get_tango_lib_release()` (*tango.Util* method), 159
- `get_tango_lib_version()` (*tango.DeviceProxy* method), 43
- `get_timeout_millis()` (*tango.DeviceProxy* method), 44
- `get_trace_level()` (*tango.Util* method), 159
- `get_transparency_reconnection()` (*tango.AttributeProxy* method), 64
- `get_transparency_reconnection()` (*tango.DeviceProxy* method), 44
- `get_type()` (*tango.Attr* method), 137
- `get_type()` (*tango.DeviceClass* method), 132
- `get_type()` (*tango.DeviceData* method), 88
- `get_user_default_properties()` (*tango.Attr* method), 137
- `get_value()` (*tango.DbHistory* method), 189
- `get_version_str()` (*tango.Util* method), 159
- `get_w_attr_by_ind()` (*tango.MultiAttribute* method), 150
- `get_w_attr_by_name()` (*tango.MultiAttribute* method), 150
- `get_writable()` (*tango.Attr* method), 137
- `get_writable()` (*tango.Attribute* method), 142
- `get_write_value()` (*tango.WAttribute* method), 147
- `get_write_value_length()` (*tango.WAttribute* method), 148
- `get_x()` (*tango.Attribute* method), 142
- `get_y()` (*tango.Attribute* method), 142
- `GreenMode` (*class in tango*), 94
- `Group` (*class in tango*), 74
- `GroupAttrReply` (*class in tango*), 80
- `GroupCmdReply` (*class in tango*), 80
- `GroupReply` (*class in tango*), 80
- ## H
- `history()` (*tango.AttributeProxy* method), 65
- ## I
- `import_device()` (*tango.Database* method), 182
- `import_info()` (*tango.DeviceProxy* method), 44
- `info()` (*tango.DeviceProxy* method), 44
- `info_stream()` (*tango.LatestDeviceImpl* method), 123
- `info_stream()` (*tango.server.Device* method), 105
- `InfoIt` (*class in tango*), 134
- `init_device()` (*tango.LatestDeviceImpl* method), 124
- `init_device()` (*tango.server.Device* method), 105
- `initialize_dynamic_attributes()` (*tango.server.Device* method), 105
- `insert()` (*tango.DeviceData* method), 88
- `is_archive_event()` (*tango.Attr* method), 137
- `is_archive_event()` (*tango.Attribute* method), 142
- `is_array_type()` (*in module tango.utils*), 197
- `is_assoc()` (*tango.Attr* method), 137
- `is_attribute_polled()` (*tango.DeviceProxy* method), 44
- `is_binary_type()` (*in module tango.utils*), 197
- `is_bool()` (*in module tango.utils*), 196
- `is_bool_type()` (*in module tango.utils*), 197
- `is_change_event()` (*tango.Attr* method), 137
- `is_change_event()` (*tango.Attribute* method), 142
- `is_check_archive_criteria()` (*tango.Attr* method), 138
- `is_check_archive_criteria()` (*tango.Attribute* method), 143
- `is_check_change_criteria()` (*tango.Attr* method), 138
- `is_check_change_criteria()` (*tango.Attribute* method), 143
- `is_command_polled()` (*tango.DeviceProxy* method), 44
- `is_control_access_checked()` (*tango.Database* method), 182
- `is_data_ready_event()` (*tango.Attr* method), 138
- `is_data_ready_event()` (*tango.Attribute* method), 143
- `is_dbase_used()` (*tango.DeviceProxy* method), 45
- `is_deleted()` (*tango.DbHistory* method), 189

- is_device_locked() (*tango.LatestDeviceImpl method*), 124
- is_device_locked() (*tango.server.Device method*), 105
- is_device_restarting() (*tango.Util method*), 159
- is_empty() (*tango.DbDatum method*), 188
- is_empty() (*tango.DeviceData method*), 88
- is_enabled() (*tango.Group method*), 77
- is_event_queue_empty() (*tango.AttributeProxy method*), 65
- is_event_queue_empty() (*tango.DeviceProxy method*), 45
- is_float_type() (*in module tango.utils*), 197
- is_int_type() (*in module tango.utils*), 197
- is_integer() (*in module tango.utils*), 196
- is_locked() (*tango.DeviceProxy method*), 45
- is_locked_by_me() (*tango.DeviceProxy method*), 45
- is_max_alarm() (*tango.Attribute method*), 143
- is_max_value() (*tango.WAttribute method*), 148
- is_max_warning() (*tango.Attribute method*), 143
- is_min_alarm() (*tango.Attribute method*), 143
- is_min_value() (*tango.WAttribute method*), 148
- is_min_warning() (*tango.Attribute method*), 143
- is_multi_tango_host() (*tango.Database method*), 182
- is_non_str_seq() (*in module tango.utils*), 196
- is_number() (*in module tango.utils*), 196
- is_numerical_type() (*in module tango.utils*), 197
- is_polled() (*tango.Attribute method*), 144
- is_polled() (*tango.AttributeProxy method*), 65
- is_polled() (*tango.LatestDeviceImpl method*), 124
- is_polled() (*tango.server.Device method*), 105
- is_pure_str() (*in module tango.utils*), 196
- is_rds_alarm() (*tango.Attribute method*), 144
- is_scalar_type() (*in module tango.utils*), 196
- is_seq() (*in module tango.utils*), 196
- is_str_type() (*in module tango.utils*), 198
- is_svr_shutting_down() (*tango.Util method*), 159
- is_svr_starting() (*tango.Util method*), 159
- is_there_subscriber() (*tango.LatestDeviceImpl method*), 124
- is_there_subscriber() (*tango.server.Device method*), 106
- is_write_associated() (*tango.Attribute method*), 144
- isoformat() (*tango.TimeVal method*), 95
- ## K
- KeepAliveCmdCode (*class in tango*), 93
- ## L
- LatestDeviceImpl (*class in tango*), 118
- lock() (*tango.DeviceProxy method*), 45
- LockCmdCode (*class in tango*), 92
- LockerInfo (*class in tango*), 86
- LockerLanguage (*class in tango*), 91
- locking_status() (*tango.DeviceProxy method*), 46
- LogIt (*class in tango*), 133
- LogLevel (*class in tango*), 92
- LogTarget (*class in tango*), 92
- ## M
- MessBoxType (*class in tango*), 91
- module
- tango, 21
 - tango.server, 96
- MultiAttribute (*class in tango*), 148
- ## N
- name() (*tango.AttributeProxy method*), 65
- name() (*tango.DeviceProxy method*), 46
- name_equals() (*tango.Group method*), 77
- name_matches() (*tango.Group method*), 77
- NamedDevFailedList, 203
- NonDbDevice, 202
- NonSupportedFeature, 202
- NotAllowed, 203
- ## O
- obj_2_str() (*in module tango.utils*), 198
- ## P
- pending_asynch_call() (*tango.ApiUtil method*), 83
- pending_asynch_call() (*tango.DeviceProxy method*), 46
- PeriodicEventInfo (*class in tango*), 90
- ping() (*tango.AttributeProxy method*), 66
- ping() (*tango.DeviceProxy method*), 46
- ping() (*tango.Group method*), 77
- pipe (*class in tango.server*), 114
- PipeWriteType (*class in tango*), 94
- poll() (*tango.AttributeProxy method*), 66
- poll_attribute() (*tango.DeviceProxy method*), 46
- poll_command() (*tango.DeviceProxy method*), 47
- PollCmdCode (*class in tango*), 92
- PollDevice (*class in tango*), 86
- polling_status() (*tango.DeviceProxy method*), 47
- PollObjType (*class in tango*), 92
- push_archive_event() (*tango.LatestDeviceImpl method*), 124
- push_archive_event() (*tango.server.Device method*), 106
- push_att_conf_event() (*tango.LatestDeviceImpl method*), 125
- push_att_conf_event() (*tango.server.Device method*), 106
- push_change_event() (*tango.LatestDeviceImpl method*), 125

- push_change_event() (*tango.server.Device method*), 107
 push_data_ready_event() (*tango.LatestDeviceImpl method*), 126
 push_data_ready_event() (*tango.server.Device method*), 107
 push_event() (*tango.LatestDeviceImpl method*), 126
 push_event() (*tango.server.Device method*), 107
 push_event() (*tango.utils.EventCallback method*), 195
 push_pipe_event() (*tango.LatestDeviceImpl method*), 127
 push_pipe_event() (*tango.server.Device method*), 108
 put_attribute_alias() (*tango.Database method*), 183
 put_class_attribute_property() (*tango.Database method*), 183
 put_class_pipe_property() (*tango.Database method*), 183
 put_class_property() (*tango.Database method*), 184
 put_device_alias() (*tango.Database method*), 184
 put_device_attribute_property() (*tango.Database method*), 184
 put_device_pipe_property() (*tango.Database method*), 184
 put_device_property() (*tango.Database method*), 185
 put_property() (*tango.AttributeProxy method*), 66
 put_property() (*tango.Database method*), 185
 put_property() (*tango.DeviceProxy method*), 47
 put_server_info() (*tango.Database method*), 186
 PYTANGO_GREEN_MODE, 13
 Python Enhancement Proposals
 PEP 249, 246, 250
- ## R
- read() (*tango.AttributeProxy method*), 66
 read_alarm() (*tango.MultiAttribute method*), 150
 read_async() (*tango.AttributeProxy method*), 67
 read_attr_hardware() (*tango.LatestDeviceImpl method*), 127
 read_attribute() (*tango.DeviceProxy method*), 48
 read_attribute() (*tango.Group method*), 77
 read_attribute_async() (*tango.DeviceProxy method*), 48
 read_attribute_async() (*tango.Group method*), 77
 read_attribute_reply() (*tango.DeviceProxy method*), 48
 read_attribute_reply() (*tango.Group method*), 77
 read_attributes() (*tango.DeviceProxy method*), 48
 read_attributes() (*tango.Group method*), 78
 read_attributes_async() (*tango.DeviceProxy method*), 49
 read_attributes_async() (*tango.Group method*), 78
 read_attributes_reply() (*tango.DeviceProxy method*), 50
 read_attributes_reply() (*tango.Group method*), 78
 read_pipe() (*tango.DeviceProxy method*), 50
 read_reply() (*tango.AttributeProxy method*), 68
 reconnect() (*tango.DeviceProxy method*), 51
 register_service() (*tango.Database method*), 186
 register_signal() (*tango.DeviceClass method*), 132
 register_signal() (*tango.LatestDeviceImpl method*), 127
 register_signal() (*tango.server.Device method*), 108
 Release (class in *tango*), 94
 remove_all() (*tango.Group method*), 78
 remove_attribute() (*tango.LatestDeviceImpl method*), 127
 remove_attribute() (*tango.server.Device method*), 108
 remove_command() (*tango.LatestDeviceImpl method*), 127
 remove_command() (*tango.server.Device method*), 108
 remove_configuration() (*tango.Attribute method*), 144
 remove_logging_target() (*tango.DeviceProxy method*), 51
 rename_server() (*tango.Database method*), 186
 requires_py Tango() (in module *tango.utils*), 198
 requires_tango() (in module *tango.utils*), 199
 reread_filedatabase() (*tango.Database method*), 186
 reset_filedatabase() (*tango.Util method*), 160
 run() (in module *tango.server*), 116
 run_server() (*tango.server.Device class method*), 109
- ## S
- scalar_to_array_type() (in module *tango.utils*), 198
 seqStr_2_obj() (in module *tango.utils*), 198
 SerialModel (class in *tango*), 92
 server_init() (*tango.Util method*), 160
 server_run() (in module *tango.server*), 117
 server_run() (*tango.Util method*), 160
 server_set_event_loop() (*tango.Util method*), 160
 set_abs_change() (*tango.UserDefaultAttrProp method*), 150

set_access_checked() (*tango.Database method*), 186
 set_access_control() (*tango.DeviceProxy method*), 51
 set_archive_abs_change() (*tango.UserDefaultAttrProp method*), 151
 set_archive_event() (*tango.Attr method*), 138
 set_archive_event() (*tango.Attribute method*), 144
 set_archive_event() (*tango.LatestDeviceImpl method*), 128
 set_archive_event() (*tango.server.Device method*), 109
 set_archive_event_abs_change() (*tango.UserDefaultAttrProp method*), 151
 set_archive_event_period() (*tango.UserDefaultAttrProp method*), 151
 set_archive_event_rel_change() (*tango.UserDefaultAttrProp method*), 151
 set_archive_period() (*tango.UserDefaultAttrProp method*), 151
 set_archive_rel_change() (*tango.UserDefaultAttrProp method*), 151
 set_assoc_ind() (*tango.Attribute method*), 144
 set_asynch_cb_sub_model() (*tango.ApiUtil method*), 83
 set_attr_serial_model() (*tango.Attribute method*), 145
 set_attribute_config() (*tango.DeviceProxy method*), 52
 set_change_event() (*tango.Attr method*), 138
 set_change_event() (*tango.Attribute method*), 145
 set_change_event() (*tango.LatestDeviceImpl method*), 128
 set_change_event() (*tango.server.Device method*), 109
 set_cl_name() (*tango.Attr method*), 138
 set_class_properties() (*tango.Attr method*), 139
 set_config() (*tango.AttributeProxy method*), 68
 set_data_ready_event() (*tango.Attr method*), 139
 set_data_ready_event() (*tango.Attribute method*), 145
 set_date() (*tango.Attribute method*), 145
 set_default_properties() (*tango.Attr method*), 139
 set_delta_t() (*tango.UserDefaultAttrProp method*), 152
 set_delta_val() (*tango.UserDefaultAttrProp method*), 152
 set_description() (*tango.UserDefaultAttrProp method*), 152
 set_disp_level() (*tango.Attr method*), 139
 set_display_unit() (*tango.UserDefaultAttrProp method*), 152
 set_enum_labels() (*tango.UserDefaultAttrProp method*), 152
 set_event_abs_change() (*tango.UserDefaultAttrProp method*), 152
 set_event_period() (*tango.UserDefaultAttrProp method*), 153
 set_event_rel_change() (*tango.UserDefaultAttrProp method*), 153
 set_format() (*tango.UserDefaultAttrProp method*), 153
 set_green_mode() (*in module tango*), 81
 set_green_mode() (*tango.DeviceProxy method*), 52
 set_label() (*tango.UserDefaultAttrProp method*), 153
 set_logging_level() (*tango.DeviceProxy method*), 52
 set_max_alarm() (*tango.UserDefaultAttrProp method*), 153
 set_max_value() (*tango.UserDefaultAttrProp method*), 153
 set_max_value() (*tango.WAttribute method*), 148
 set_max_warning() (*tango.UserDefaultAttrProp method*), 154
 set_memorized() (*tango.Attr method*), 139
 set_memorized_init() (*tango.Attr method*), 139
 set_min_alarm() (*tango.UserDefaultAttrProp method*), 154
 set_min_value() (*tango.UserDefaultAttrProp method*), 154
 set_min_value() (*tango.WAttribute method*), 148
 set_min_warning() (*tango.UserDefaultAttrProp method*), 154
 set_period() (*tango.UserDefaultAttrProp method*), 154
 set_pipe_config() (*tango.DeviceProxy method*), 53
 set_polling_period() (*tango.Attr method*), 140
 set_polling_threads_pool_size() (*tango.Util method*), 161
 set_properties() (*tango.Attribute method*), 145
 set_quality() (*tango.Attribute method*), 146
 set_rel_change() (*tango.UserDefaultAttrProp method*), 154
 set_serial_model() (*tango.Util method*), 161
 set_server_version() (*tango.Util method*), 161
 set_source() (*tango.DeviceProxy method*), 53

- set_standard_unit() (*tango.UserDefaultAttrProp method*), 154
 set_state() (*tango.LatestDeviceImpl method*), 128
 set_state() (*tango.server.Device method*), 109
 set_status() (*tango.LatestDeviceImpl method*), 128
 set_status() (*tango.server.Device method*), 110
 set_timeout_millis() (*tango.DeviceProxy method*), 53
 set_timeout_millis() (*tango.Group method*), 78
 set_trace_level() (*tango.Util method*), 161
 set_transparency_reconnection() (*tango.AttributeProxy method*), 69
 set_transparency_reconnection() (*tango.DeviceProxy method*), 54
 set_type() (*tango.DeviceClass method*), 133
 set_unit() (*tango.UserDefaultAttrProp method*), 155
 set_value() (*tango.Attribute method*), 146
 set_value_date_quality() (*tango.Attribute method*), 146
 set_w_dim_x() (*tango.DeviceAttribute method*), 87
 set_w_dim_y() (*tango.DeviceAttribute method*), 87
 signal_handler() (*tango.DeviceClass method*), 133
 signal_handler() (*tango.LatestDeviceImpl method*), 128
 signal_handler() (*tango.server.Device method*), 110
 size() (*tango.DbDatum method*), 188
 state() (*tango.AttributeProxy method*), 69
 state() (*tango.DeviceProxy method*), 54
 status() (*tango.AttributeProxy method*), 69
 status() (*tango.DeviceProxy method*), 54
 stop_poll() (*tango.AttributeProxy method*), 69
 stop_poll_attribute() (*tango.DeviceProxy method*), 54
 stop_poll_command() (*tango.DeviceProxy method*), 54
 stop_polling() (*tango.LatestDeviceImpl method*), 129
 stop_polling() (*tango.server.Device method*), 110
 strftime() (*tango.TimeVal method*), 95
 subscribe_event() (*tango.AttributeProxy method*), 69
 subscribe_event() (*tango.DeviceProxy method*), 54
- T**
- tango
 module, 21
 tango.server
 module, 96
- TANGO_HOST, 3, 4, 205
 TimeVal (class in *tango*), 95
 todatetime() (*tango.TimeVal method*), 95
 totime() (*tango.TimeVal method*), 95
 trigger_attr_polling() (*tango.Util method*), 161
 trigger_cmd_polling() (*tango.Util method*), 161
- U**
- unexport_device() (*tango.Database method*), 187
 unexport_event() (*tango.Database method*), 187
 unexport_server() (*tango.Database method*), 187
 unlock() (*tango.DeviceProxy method*), 56
 unregister_server() (*tango.Util method*), 162
 unregister_service() (*tango.Database method*), 187
 unregister_signal() (*tango.DeviceClass method*), 133
 unregister_signal() (*tango.LatestDeviceImpl method*), 129
 unregister_signal() (*tango.server.Device method*), 110
 unsubscribe_event() (*tango.AttributeProxy method*), 71
 unsubscribe_event() (*tango.DeviceProxy method*), 56
 UserDefaultAttrProp (class in *tango*), 150
 Util (class in *tango*), 155
- W**
- warn_stream() (*tango.LatestDeviceImpl method*), 129
 warn_stream() (*tango.server.Device method*), 110
 WarnIt (class in *tango*), 135
 WAttribute (class in *tango*), 147
 write() (*tango.AttributeProxy method*), 72
 write_async() (*tango.AttributeProxy method*), 72
 write_attr_hardware() (*tango.LatestDeviceImpl method*), 129
 write_attr_hardware() (*tango.server.Device method*), 111
 write_attribute() (*tango.DeviceProxy method*), 56
 write_attribute() (*tango.Group method*), 79
 write_attribute_async() (*tango.DeviceProxy method*), 57
 write_attribute_async() (*tango.Group method*), 79
 write_attribute_reply() (*tango.DeviceProxy method*), 57
 write_attribute_reply() (*tango.Group method*), 79
 write_attributes() (*tango.DeviceProxy method*), 58

`write_attributes_async()`
 (*tango.DeviceProxy method*), 58
`write_attributes_reply()`
 (*tango.DeviceProxy method*), 59
`write_filedatabase()` (*tango.Database*
 method), 187
`write_pipe()` (*tango.DeviceProxy method*), 59
`write_read()` (*tango.AttributeProxy method*), 73
`write_read_attribute()` (*tango.DeviceProxy*
 method), 60
`write_read_attributes()` (*tango.DeviceProxy*
 method), 60
`write_reply()` (*tango.AttributeProxy method*), 73
WrongData, 202
WrongNameSyntax, 201